



Vimba

Vimba 1394 TL Features Manual

1.4.2

Legal Notice

Trademarks

Unless stated otherwise, all trademarks appearing in this document of Allied Vision Technologies are brands protected by law.

Warranty

The information provided by Allied Vision is supplied without any guarantees or warranty whatsoever, be it specific or implicit. Also excluded are all implicit warranties concerning the negotiability, the suitability for specific applications or the non-breaking of laws and patents. Even if we assume that the information supplied to us is accurate, errors and inaccuracy may still occur.

Copyright

All texts, pictures and graphics are protected by copyright and other laws protecting intellectual property. It is not permitted to copy or modify them for trade use or transfer, nor may they be used on websites.

Allied Vision Technologies GmbH 02/2016

All rights reserved.

Managing Director: Mr. Frank Grube

Tax ID: DE 184383113

Headquarters:

Taschenweg 2a

D-07646 Stadtroda, Germany

Tel.: +49 (0)36428 6770

Fax: +49 (0)36428 677-28

e-mail: info@alliedvision.com

Contents

| | | |
|----------|--|-----------|
| 1 | Contacting Allied Vision | 12 |
| 2 | Document history and conventions | 13 |
| 2.1 | Document history | 14 |
| 2.2 | Conventions used in this manual | 14 |
| 2.2.1 | Styles | 14 |
| 2.2.2 | Symbols | 15 |
| 3 | Vimba1394TL - Overview | 16 |
| 4 | Vimba1394TL System Features | 17 |
| 4.1 | SystemInformation | 18 |
| 4.1.1 | TLVendorName | 18 |
| 4.1.2 | TLModelName | 18 |
| 4.1.3 | TLID | 19 |
| 4.1.4 | TLDisplayName | 19 |
| 4.1.5 | TLVersion | 20 |
| 4.1.6 | TLPath | 20 |
| 4.1.7 | TLType | 20 |
| 4.1.8 | GenTLVersionMajor | 21 |
| 4.1.9 | GenTLVersionMinor | 21 |
| 4.1.10 | GenTLSFNCVersionMajor | 22 |
| 4.1.11 | GenTLSFNCVersionMinor | 22 |
| 4.1.12 | GenTLSFNCVersionSubMinor | 22 |
| 4.2 | InterfaceEnumeration | 23 |
| 4.2.1 | InterfaceUpdateList | 23 |
| 4.2.2 | InterfaceCount [Allied Vision] | 23 |
| 4.2.3 | InterfaceSelector | 24 |
| 4.2.4 | InterfaceID | 24 |
| 4.2.5 | InterfaceDisplayName [Allied Vision] | 24 |
| 5 | Vimba1394TL Interface Features | 25 |
| 5.1 | InterfaceInformation | 26 |
| 5.1.1 | InterfaceID | 26 |
| 5.1.2 | InterfaceType | 26 |
| 5.1.3 | InterfaceDisplayName | 27 |
| 5.2 | DeviceEnumeration | 27 |
| 5.2.1 | DeviceUpdateList | 27 |
| 5.2.2 | DeviceCount [Allied Vision] | 28 |
| 5.2.3 | DeviceSelector | 28 |

| | | |
|----------|--|-----------|
| 5.2.4 | DeviceID | 28 |
| 5.2.5 | DeviceDisplayName [Allied Vision] | 29 |
| 5.2.6 | DeviceVendorName | 29 |
| 5.2.7 | DeviceModelName | 29 |
| 5.2.8 | DeviceType [Allied Vision] | 30 |
| 5.2.9 | DeviceAccessStatus | 30 |
| 6 | Vimba1394TL Device Features | 31 |
| 6.1 | DeviceInformation | 32 |
| 6.1.1 | DeviceID | 32 |
| 6.1.2 | DeviceVendorName | 32 |
| 6.1.3 | DeviceModelName | 33 |
| 6.1.4 | DeviceType | 33 |
| 6.1.5 | DeviceDisplayName | 34 |
| 6.2 | StreamEnumeration | 34 |
| 6.2.1 | StreamCount [Allied Vision] | 34 |
| 6.2.2 | StreamSelector | 35 |
| 6.2.3 | StreamID | 35 |
| 7 | Vimba1394TL DataStream Features | 36 |
| 7.1 | StreamInformation | 37 |
| 7.1.1 | StreamID | 37 |
| 7.1.2 | StreamType | 37 |
| 7.1.3 | StreamIsGrabbing [Allied Vision] | 38 |
| 7.2 | BufferHandlingControl | 38 |
| 7.2.1 | StreamAnnouncedBufferCount | 38 |
| 7.2.2 | StreamBufferHandlingMode | 39 |
| 7.2.3 | StreamAnnounceBufferMinimum | 39 |
| 7.2.4 | DriverBuffersCount [Allied Vision] | 39 |
| 8 | Vimba1394TL Camera Features | 41 |
| 8.1 | 1394 registers, FireGrab parameters and the Vimba1394TL features | 42 |
| 8.2 | DeviceControl | 44 |
| 8.2.1 | DeviceVendorName | 44 |
| 8.2.2 | DeviceModelName | 44 |
| 8.2.3 | DeviceFirmwareVersion | 45 |
| 8.2.4 | FirmwareVerMajor [Allied Vision] | 45 |
| 8.2.5 | FirmwareVerMinor [Allied Vision] | 45 |
| 8.2.6 | FirmwareVerBuild [Allied Vision] | 46 |
| 8.2.7 | DeviceMicrocontrollerVersion [Allied Vision] | 46 |
| 8.2.8 | DeviceSFNCVersionMajor | 46 |
| 8.2.9 | DeviceSFNCVersionMinor | 47 |

| | | |
|--------|---|----|
| 8.2.10 | DeviceSFNCVersionSubMinor | 47 |
| 8.2.11 | DeviceID | 47 |
| 8.2.12 | DeviceSerialNumber [Allied Vision] | 48 |
| 8.2.13 | DeviceScanType | 48 |
| 8.2.14 | DeviceStatusLightEnable [Allied Vision] | 48 |
| 8.2.15 | DeviceAccessRegisterAddress [Allied Vision] | 49 |
| 8.2.16 | DeviceAccessRegisterValue [Allied Vision] | 49 |
| 8.3 | ImageFormatControl | 49 |
| 8.3.1 | SensorWidth | 50 |
| 8.3.2 | SensorHeight | 50 |
| 8.3.3 | SensorTaps | 51 |
| 8.3.4 | SensorDigitizationTaps | 51 |
| 8.3.5 | SensorBits [Allied Vision] | 51 |
| 8.3.6 | Width | 52 |
| 8.3.7 | Height | 52 |
| 8.3.8 | WidthMax | 52 |
| 8.3.9 | HeightMax | 53 |
| 8.3.10 | OffsetX | 53 |
| 8.3.11 | OffsetY | 54 |
| 8.3.12 | BinningHorizontal | 54 |
| 8.3.13 | BinningVertical | 55 |
| 8.3.14 | DecimationHorizontal | 55 |
| 8.3.15 | DecimationVertical | 56 |
| 8.3.16 | ReverseX | 56 |
| 8.3.17 | ReverseY | 56 |
| 8.3.18 | PixelFormat | 57 |
| 8.3.19 | PixelColorFilter | 57 |
| 8.3.20 | PixelColorFilterAuto [Allied Vision] | 58 |
| 8.3.21 | ImageSize [Allied Vision] | 58 |
| 8.3.22 | TestImageSelector | 59 |
| 8.3.23 | IIDCActivateFormat7 [Allied Vision] | 59 |
| 8.3.24 | IIDCMode [Allied Vision] | 60 |
| 8.3.25 | IIDCModeDescription [Allied Vision] | 60 |
| 8.4 | AcquisitionControl | 62 |
| 8.4.1 | AcquisitionMode | 62 |
| 8.4.2 | AcquisitionStart | 63 |
| 8.4.3 | AcquisitionStop | 63 |
| 8.4.4 | AcquisitionAbort | 63 |
| 8.4.5 | AcquisitionFrameCount | 64 |
| 8.4.6 | AcquisitionFrameRate | 64 |
| 8.4.7 | AcquisitionFrameRateLimit [Allied Vision] | 65 |

| | | |
|--------|--|----|
| 8.4.8 | DeferredTransportDisable [Allied Vision] | 65 |
| 8.4.9 | HighSNRImages [Allied Vision] | 65 |
| 8.4.10 | TriggerSelector | 66 |
| 8.4.11 | TriggerMode | 66 |
| 8.4.12 | TriggerSoftware | 67 |
| 8.4.13 | TriggerSource | 67 |
| 8.4.14 | TriggerActivation | 68 |
| 8.4.15 | TriggerDelay | 68 |
| 8.4.16 | ExposureMode | 69 |
| 8.4.17 | ExposureTime | 69 |
| 8.4.18 | ExposureOffset [Allied Vision] | 70 |
| 8.4.19 | ExposureTimeRaw | 70 |
| 8.4.20 | ExposureAuto | 70 |
| 8.5 | ExposureAutoControl [Allied Vision] | 71 |
| 8.5.1 | ExposureAutoTimebase [Allied Vision] | 71 |
| 8.5.2 | ExposureAutoMin [Allied Vision] | 72 |
| 8.5.3 | ExposureAutoMax [Allied Vision] | 72 |
| 8.5.4 | ExposureAutoTarget [Allied Vision] | 73 |
| 8.5.5 | ExposureAutoAlg [Allied Vision] | 73 |
| 8.6 | DigitalIOControl | 73 |
| 8.6.1 | LineSelector | 74 |
| 8.6.2 | LineMode | 74 |
| 8.6.3 | LineInverter | 75 |
| 8.6.4 | LineStatus | 75 |
| 8.6.5 | LineSource | 75 |
| 8.6.6 | LineRouting [Allied Vision] | 76 |
| 8.6.7 | LineFormat | 77 |
| 8.6.8 | LineDebounceTime [Allied Vision] | 77 |
| 8.6.9 | LineModulationPulseWidth [Allied Vision] | 77 |
| 8.6.10 | LineModulationPeriod [Allied Vision] | 78 |
| 8.6.11 | IntEnaDelayTime [Allied Vision] | 78 |
| 8.6.12 | IntEnaDelayEnable [Allied Vision] | 79 |
| 8.7 | SerialPortControl [Allied Vision] | 79 |
| 8.7.1 | SerialPortSelector [Allied Vision] | 79 |
| 8.7.2 | SerialPortModeSelector [Allied Vision] | 80 |
| 8.7.3 | SerialPortBaudRate [Allied Vision] | 80 |
| 8.7.4 | SerialPortCharLength [Allied Vision] | 80 |
| 8.7.5 | SerialPortParity [Allied Vision] | 81 |
| 8.7.6 | SerialPortStopBits [Allied Vision] | 81 |
| 8.7.7 | SerialPortTransmitReady [Allied Vision] | 82 |
| 8.7.8 | SerialPortReceiveReady [Allied Vision] | 82 |

| | | |
|---------|--|----|
| 8.7.9 | SerialPortReceiveOverrunError [Allied Vision] | 82 |
| 8.7.10 | SerialPortReceiveFramingError [Allied Vision] | 83 |
| 8.7.11 | SerialPortReceiveParityError [Allied Vision] | 83 |
| 8.7.12 | SerialPortBuffer [Allied Vision] | 83 |
| 8.7.13 | SerialPortValidReceiveSize [Allied Vision] | 84 |
| 8.7.14 | SerialPortRemainingReceiveSize [Allied Vision] | 84 |
| 8.7.15 | SerialPortTransmitSize [Allied Vision] | 84 |
| 8.8 | AnalogControl | 85 |
| 8.8.1 | GainSelector | 85 |
| 8.8.2 | Gain | 85 |
| 8.8.3 | GainRaw | 86 |
| 8.8.4 | GainAuto | 86 |
| 8.8.5 | GainAutoTarget [Allied Vision] | 87 |
| 8.8.6 | BlackLevelSelector | 87 |
| 8.8.7 | BlackLevel | 87 |
| 8.8.8 | Gamma | 88 |
| 8.8.9 | GammaRaw [Allied Vision] | 88 |
| 8.8.10 | BalanceRatioSelector | 89 |
| 8.8.11 | BalanceRatioRaw [Allied Vision] | 89 |
| 8.8.12 | BalanceWhiteAuto | 90 |
| 8.9 | LUTControl | 90 |
| 8.9.1 | LUTSelector | 91 |
| 8.9.2 | LUTEnable | 91 |
| 8.9.3 | LUTCount [Allied Vision] | 92 |
| 8.9.4 | LUTSizeBytes [Allied Vision] | 92 |
| 8.9.5 | LUTBitDepthIn [Allied Vision] | 92 |
| 8.9.6 | LUTBitDepthOut [Allied Vision] | 93 |
| 8.10 | TransportLayerControl | 93 |
| 8.10.1 | PayloadSize | 94 |
| 8.10.2 | IIDCPHyspeed [Allied Vision] | 94 |
| 8.10.3 | IIDCFreeBandwidth [Allied Vision] | 95 |
| 8.10.4 | IIDCPacketSizeMaximum [Allied Vision] | 95 |
| 8.10.5 | IIDCUseStandardPacketSizeMaximum [Allied Vision] | 95 |
| 8.10.6 | IIDCPacketSizeAuto [Allied Vision] | 96 |
| 8.10.7 | IIDCPacketSize [Allied Vision] | 96 |
| 8.10.8 | IIDCPacketCount [Allied Vision] | 97 |
| 8.10.9 | IIDCCameraAcceptDelay [Allied Vision] | 97 |
| 8.10.10 | IIDCIsoChannelAuto [Allied Vision] | 97 |
| 8.10.11 | IIDCIsoChannel [Allied Vision] | 98 |
| 8.10.12 | IIDCBusNumber [Allied Vision] | 98 |
| 8.11 | UserSetControl | 98 |

| | | |
|---------|---|-----|
| 8.11.1 | UserSetSelector | 99 |
| 8.11.2 | UserSetLoad | 99 |
| 8.11.3 | UserSetSave | 99 |
| 8.11.4 | UserSetMakeDefault [Allied Vision] | 100 |
| 8.11.5 | UserSetOperationStatus [Allied Vision] | 100 |
| 8.11.6 | UserSetOperationResult [Allied Vision] | 100 |
| 8.12 | FileAccessControl | 101 |
| 8.12.1 | FileSelector | 101 |
| 8.12.2 | FileStatus [Allied Vision] | 102 |
| 8.12.3 | FileOperationSelector | 102 |
| 8.12.4 | FileOperationExecute | 103 |
| 8.12.5 | FileOpenMode | 103 |
| 8.12.6 | FileAccessBuffer | 103 |
| 8.12.7 | FileAccessOffset | 104 |
| 8.12.8 | FileAccessLength | 104 |
| 8.12.9 | FileOperationStatus | 105 |
| 8.12.10 | FileOperationResult | 105 |
| 8.12.11 | FileSize | 105 |
| 8.13 | ColorTransformationControl | 106 |
| 8.13.1 | ColorTransformationSelector | 106 |
| 8.13.2 | ColorTransformationEnable | 106 |
| 8.13.3 | ColorTransformationReset [Allied Vision] | 107 |
| 8.13.4 | ColorTransformationValueSelector | 107 |
| 8.13.5 | ColorTransformationValue | 107 |
| 8.13.6 | Hue [Allied Vision] | 108 |
| 8.13.7 | HueRaw [Allied Vision] | 108 |
| 8.13.8 | HueEnable [Allied Vision] | 108 |
| 8.13.9 | Saturation [Allied Vision] | 109 |
| 8.13.10 | SaturationRaw [Allied Vision] | 109 |
| 8.13.11 | SaturationEnable [Allied Vision] | 110 |
| 8.14 | AutofunctionControl [Allied Vision] | 110 |
| 8.14.1 | AutofunctionTargetIntensity [Allied Vision] | 110 |
| 8.14.2 | AutofunctionAOIEnable [Allied Vision] | 111 |
| 8.14.3 | AutofunctionAOIShowArea [Allied Vision] | 111 |
| 8.14.4 | AutofunctionAOIWidth [Allied Vision] | 111 |
| 8.14.5 | AutofunctionAOIHeight [Allied Vision] | 112 |
| 8.14.6 | AutofunctionAOIOffsetX [Allied Vision] | 112 |
| 8.14.7 | AutofunctionAOIOffsetY [Allied Vision] | 112 |
| 8.15 | ImageQualityControl [Allied Vision] | 113 |
| 8.15.1 | ShadingCorrectionEnable [Allied Vision] | 113 |
| 8.15.2 | ShadingCorrectionShowData [Allied Vision] | 113 |

| | | |
|----------|---|------------|
| 8.15.3 | ShadingDataBuildImages [Allied Vision] | 114 |
| 8.15.4 | ShadingDataBuild [Allied Vision] | 114 |
| 8.15.5 | ShadingDataLoadFromFlash [Allied Vision] | 114 |
| 8.15.6 | ShadingDataSaveToFlash [Allied Vision] | 115 |
| 8.15.7 | ShadingDataClearFlash [Allied Vision] | 115 |
| 8.15.8 | ShadingDataMaxSize [Allied Vision] | 115 |
| 8.15.9 | SmearReductionEnable [Allied Vision] | 116 |
| 9 | Vimba functional extensions to GenTL | 117 |
| 9.1 | Custom Transport Layer events | 118 |
| 9.1.1 | Additions to EVENT_TYPE_LIST | 118 |
| 9.1.2 | Additions to EVENT_DATA_INFO_CMD_LIST | 118 |
| 9.1.3 | Additional enumeration IFCHANGE_WHAT_LIST | 118 |
| 9.2 | Additional URL information | 119 |
| 9.2.1 | Additions to URL_INFO_CMD_LIST | 119 |

List of Tables

| | | |
|---|--|----|
| 1 | Translation of feature values known from IIDC/FireGrab | 43 |
|---|--|----|

Listings

| | | |
|---|--------------------------------|-----|
| 1 | Event types | 118 |
| 2 | Change Events | 118 |
| 3 | Change Event options | 119 |
| 4 | URL information | 119 |

1 Contacting Allied Vision

Connect with Allied Vision by function

<https://www.alliedvision.com/en/meta-header/contact>

Find an Allied Vision office or distributor

<https://www.alliedvision.com/en/about-us/where-we-are>

Email

info@alliedvision.com
support@alliedvision.com

Telephone

EMEA: +49 36428-677-0
The Americas: +1 978-225-2030
Asia-Pacific: +65 6634-9027
China: +86 (21) 64861133

Headquarters

Allied Vision Technologies GmbH
Taschenweg 2a
07646 Stadtroda
Germany

Tel: +49 (0)36428 677-0
Fax: +49 (0)36428 677-28
President/CEO: Frank Grube
Registration Office: AG Jena HRB 208962

2 Document history and conventions



This chapter includes:

| | | |
|-------|---|----|
| 2.1 | Document history | 14 |
| 2.2 | Conventions used in this manual | 14 |
| 2.2.1 | Styles | 14 |
| 2.2.2 | Symbols | 15 |

2.1 Document history

| Version | Date | Changes |
|---------|-------------|---|
| 1.0 | 2013-01-15 | Initial version |
| 1.1 | 2013-03-07 | Added more detailed category information, changed the layout |
| 1.2 | 2013-06-05 | Refined many descriptions, changed the document layout as well as the table layout for the features |
| 1.3 | 2014-07-10 | Changes due to GenTL 1.3 compliance, added chapter for finding camera features |
| 1.4.1 | 2015-11-09 | Renamed several Vimba components and documents ("AVT" no longer in use), links to new Allied Vision website |
| 1.4.2 | 2016-Feb-29 | New document layout |

2.2 Conventions used in this manual

To give this manual an easily understood layout and to emphasize important information, the following typographical styles and symbols are used:

2.2.1 Styles

| Style | Function | Example |
|--------------------|--|--------------------------|
| Emphasis | Programs, or highlighting important things | Emphasis |
| Publication title | Publication titles | <i>Title</i> |
| Web reference | Links to web pages | Link |
| Document reference | Links to other documents | Document |
| Output | Outputs from software GUI | Output |
| Input | Input commands, modes | <i>Input</i> |
| Feature | Feature names | Feature |

2.2.2 Symbols



Practical Tip



Safety-related instructions to avoid malfunctions

Instructions to avoid malfunctions



Further information available online

3 Vimba1394TL - Overview

The Vimba1394TL (Vimba 1394 Transport Layer) transports the data from the FireWire interface card to an application. It complies with GenICam and thus can serve as a GenTL (GenICam transport layer) producer for applications providing a GenTL consumer interface. The Vimba1394TL can be included during the Vimba installation on Windows and supports both 1394a and 1394b cameras from Allied Vision.



The mandatory 1394 device driver and the required hardware drivers must be installed separately. See Vimba Manual, chapter Vimba Driver Installer.

The Vimba1394TL consists of several parts: the functional interface, the feature maps, and a configuration file.


The **functional interface** is needed for dynamically controlling 1394 cameras. It covers the complete functionality described in [GenTL specification 1.3](#). There is extra functionality, which is described in chapter Vimba functional extensions to GenTL.

The **features** exposed by XML files are GenAPI-conforming features described in the following chapters and documents:

- Features of the GenTL **System module** in chapter Vimba1394TL System Features. The System is a module for handling multiple GenTL Interfaces in one transport layer. The Vimba1394TL only provides one Interface.
- Features of the GenTL **Interface module** in chapter Vimba1394TL Interface Features. The Interface is a module for handling multiple GenTL Devices. In this case, all the devices are attached to the same Interface.
- Features of the GenTL **Device module** in chapter Vimba1394TL Device Features. The Device module is a host-side representation of the Camera also known as **Remote Device**.
- Features of the GenTL **Data Stream module** in chapter Vimba1394TL DataStream Features. The Data Stream module allows handling all streaming-related operations.
- Camera (**Remote Device**) features in chapter Vimba1394TL Camera Features. The features listed in this chapter are the ones that are available if the camera in use supports them. Additional feature documentation for the Remote Device can be found in the [GenICam Standard Features Naming Convention, version 1.5.1](#).

The **configuration file**, which is named Vimba1394TL.xml (according to the name of the Vimba1394TL.cti), must be in the same directory as the Transport Layer file. The configuration options are described in the comments of the file itself.

4 Vimba1394TL System Features



This chapter includes:

| | | |
|--------|--------------------------------------|----|
| 4.1 | SystemInformation | 18 |
| 4.1.1 | TLVendorName | 18 |
| 4.1.2 | TLModelName | 18 |
| 4.1.3 | TLID | 19 |
| 4.1.4 | TLDisplayName | 19 |
| 4.1.5 | TLVersion | 20 |
| 4.1.6 | TLPath | 20 |
| 4.1.7 | TLType | 20 |
| 4.1.8 | GenTLVersionMajor | 21 |
| 4.1.9 | GenTLVersionMinor | 21 |
| 4.1.10 | GenTLFNCVersionMajor | 22 |
| 4.1.11 | GenTLFNCVersionMinor | 22 |
| 4.1.12 | GenTLFNCVersionSubMinor | 22 |
| 4.2 | InterfaceEnumeration | 23 |
| 4.2.1 | InterfaceUpdateList | 23 |
| 4.2.2 | InterfaceCount [Allied Vision] | 23 |
| 4.2.3 | InterfaceSelector | 24 |
| 4.2.4 | InterfaceID | 24 |
| 4.2.5 | InterfaceDisplayName [Allied Vision] | 24 |

This chapter lists features that are potentially available in this module. Some features are only available under certain circumstances.

The following categories can be found below the Root category:

- SystemInformation
- InterfaceEnumeration

4.1 SystemInformation

Category that contains all System Information features of the System module.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.1 TLVendorName

| Name | TL Vendor Name |
|-------------------|----------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Name of the GenTL Producer vendor.

Corresponds to the TL_INFO_VENDOR command of TLGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.2 TLModelName

| Name | TL Model Name |
|-------------------|---------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Name of the GenTL Producer to distinguish different kinds of GenTL Producer implementations from one vendor.

Corresponds to the TL_INFO_MODEL command of TLGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.3 TLID

| Name | TL ID |
|-------------------|---------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

Unique identifier of the GenTL Producer like a GUID.

Corresponds to the TL_INFO_ID command of TLGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.4 TLDisplayName

| Name | TL Display Name |
|-------------------|-----------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

User readable name of the GenTL Producer.

Corresponds to the TL_INFO_DISPLAYNAME command of TLGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.5 TLVersion

| Name | TL Version |
|-------------------|------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Vendor specific version string.

Corresponds to the TL_INFO_VERSION command of TLGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.6 TLPath

| Name | TL Path |
|-------------------|---------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

Full path to the GenTL Producer driver including name and extension.

Corresponds to the TL_INFO_PATHNAME command of TLGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.7 TLType

| Name | TL Type |
|-------------------|--------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | IIDC |

Transport layer type of the GenTL Producer implementation.
Corresponds to the TL_INFO_TLTYPE command of TLGetInfo function.
See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.8 GenTLVersionMajor

| Name | GenTL Version Major |
|------------|---------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Major version number of the GenTL specification the GenTL Producer implementation complies with.
See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.9 GenTLVersionMinor

| Name | GenTL Version Minor |
|------------|---------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Minor version number of the GenTL specification the GenTL Producer implementation complies with.
See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.10 GenTL SFNC Version Major

| Name | GenTL SFNC Version Major |
|------------|--------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Major version number of the GenTL Standard Features Naming Convention that was used to create the GenTL Producer's XML.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.11 GenTL SFNC Version Minor

| Name | GenTL SFNC Version Minor |
|------------|--------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Minor version number of the GenTL Standard Features Naming Convention that was used to create the GenTL Producer's XML.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.1.12 GenTL SFNC Version Sub Minor

| Name | GenTL SFNC Version Sub Minor |
|------------|------------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Sub minor version number of the GenTL Standard Features Naming Convention that was used to create the GenTL Producer's XML.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.2 InterfaceEnumeration

Category that contains all Interface Enumeration features of the System module.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.2.1 InterfaceUpdateList

| Name | Interface Update List |
|------------|-----------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Expert |

Update the interface list on this GenTL Producer.

See [GenTL specification 1.3 chapter 7](#) for more details.

4.2.2 InterfaceCount [Allied Vision]

| Name | Interface Count |
|------------|-----------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Number of interfaces on this GenTL Producer.

4.2.3 InterfaceSelector

| Name | Interface Selector |
|------------|--------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |
| Values | 0.. |

Selector for the different GenTL Producer interfaces.
See [GenTL specification 1.3 chapter 7](#) for more details.

4.2.4 InterfaceID

| Name | Interface ID |
|------------|--------------|
| Interface | String |
| Access | Read |
| Visibility | Expert |


GenTL Producer wide unique identifier of the selected interface.
See [GenTL specification 1.3 chapter 7](#) for more details.

4.2.5 InterfaceDisplayName [Allied Vision]

| Name | Interface Display Name |
|------------|------------------------|
| Interface | String |
| Access | Read |
| Visibility | Expert |

User readable name of the selected interface.

5 Vimba1394TL Interface Features



This chapter includes:

| | | |
|-------|---|----|
| 5.1 | InterfaceInformation | 26 |
| 5.1.1 | InterfaceID | 26 |
| 5.1.2 | InterfaceType | 26 |
| 5.1.3 | InterfaceDisplayName | 27 |
| 5.2 | DeviceEnumeration | 27 |
| 5.2.1 | DeviceUpdateList | 27 |
| 5.2.2 | DeviceCount [Allied Vision] | 28 |
| 5.2.3 | DeviceSelector | 28 |
| 5.2.4 | DeviceID | 28 |
| 5.2.5 | DeviceDisplayName [Allied Vision] | 29 |
| 5.2.6 | DeviceVendorName | 29 |
| 5.2.7 | DeviceModelName | 29 |
| 5.2.8 | DeviceType [Allied Vision] | 30 |
| 5.2.9 | DeviceAccessStatus | 30 |

This chapter lists features that are potentially available in this module. Some features are only available under certain circumstances.

The following categories can be found below the Root category:

- InterfaceInformation
- DeviceEnumeration

5.1 InterfaceInformation

Category that contains all Interface Information features of the Interface module.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.1.1 InterfaceID

| Name | Interface ID |
|-------------------|--------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

GenTL Producer wide unique identifier of the selected interface.
Corresponds to the INTERFACE_INFO_ID command of IFGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.1.2 InterfaceType

| Name | Interface Type |
|-------------------|----------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | IIDC |

Transport layer type of the interface.

Corresponds to the `INTERFACE_INFO_TLTYPE` command of `IFGetInfo` function.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.1.3 InterfaceDisplayName

| Name | Interface Display Name |
|------------|------------------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

User readable name of the selected interface.

Corresponds to the `INTERFACE_INFO_DISPLAYNAME` command of `IFGetInfo` function.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2 DeviceEnumeration

Category that contains all Device Enumeration features of the Interface module.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2.1 DeviceUpdateList

| Name | Device Update List |
|------------|--------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Expert |

Updates the internal device list.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2.2 DeviceCount [Allied Vision]

| Name | Device Count |
|------------|--------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Number of found devices.

5.2.3 DeviceSelector

| Name | Device Selector |
|------------|-----------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |
| Values | 0.. |

Selector for the different devices on this interface.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2.4 DeviceID

| Name | Device ID |
|------------|-----------|
| Interface | String |
| Access | Read |
| Visibility | Expert |

Interface wide unique identifier of the selected device.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2.5 DeviceDisplayName [Allied Vision]

| Name | Device Display Name |
|------------|---------------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

User readable name of the selected device.

5.2.6 DeviceVendorName

| Name | Device Vendor Name |
|------------|--------------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

Name of the device vendor.

Corresponds to the "DeviceVendorName" feature of the remote device.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2.7 DeviceModelName

| Name | Device Model Name |
|------------|-------------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

Name of the device model.

Corresponds to the "DeviceModelName" feature of the remote device.

See [GenTL specification 1.3 chapter 7](#) for more details.

5.2.8 DeviceType [Allied Vision]

| Name | Device Type |
|-------------------|--------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | IIDC |

Identifies the transport layer technology of the device.
Possible values:


- IIDC: IIDC 1394

5.2.9 DeviceAccessStatus

| Name | Device Access Status |
|-------------------|-------------------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | ReadWrite, ReadOnly, NoAccess |

Gives the device's access status at the moment of the last execution of “DeviceUpdateList”.
See [GenTL specification 1.3 chapter 7](#) for more details.

6 Vimba1394TL Device Features



This chapter includes:

| | | |
|-------|---------------------------------------|----|
| 6.1 | DeviceInformation | 32 |
| 6.1.1 | DeviceID | 32 |
| 6.1.2 | DeviceVendorName | 32 |
| 6.1.3 | DeviceModelName | 33 |
| 6.1.4 | DeviceType | 33 |
| 6.1.5 | DeviceDisplayName | 34 |
| 6.2 | StreamEnumeration | 34 |
| 6.2.1 | StreamCount [Allied Vision] | 34 |
| 6.2.2 | StreamSelector | 35 |
| 6.2.3 | StreamID | 35 |

This chapter lists features that are potentially available in this module. Some features are only available under certain circumstances.

The following categories can be found below the Root category:

- DeviceInformation
- StreamEnumeration

6.1 DeviceInformation

Category that contains all Device Information features of the Device module.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.1.1 DeviceID

| Name | Device ID |
|-------------------|-----------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

Interface-wide unique identifier of this device.

Corresponds to the DEVICE_INFO_ID command of DevGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.1.2 DeviceVendorName

| Name | Device Vendor Name |
|-------------------|--------------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Name of the device vendor.

Corresponds to the `DEVICE_INFO_VENDOR` command of `DevGetInfo` function.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.1.3 DeviceModelName

| Name | Device Model Name |
|-------------------|-------------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Name of the device model.

Corresponds to the `DEVICE_INFO_MODEL` command of `DevGetInfo` function.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.1.4 DeviceType

| Name | Device Type |
|-------------------|--------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | IIDC |

Transport layer type of the device.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.1.5 DeviceDisplayName

| Name | Device Display Name |
|------------|---------------------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

User readable name of the device.

Corresponds to the `DEVICE_INFO_DISPLAYNAME` command of `DevGetInfo` function.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.2 StreamEnumeration

Category that contains all Stream Enumeration features of the Device module.

See [GenTL specification 1.3 chapter 7](#) for more details.

6.2.1 StreamCount [Allied Vision]

| Name | Stream Count |
|------------|--------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Number of available streams.

6.2.2 StreamSelector

| Name | Stream Selector |
|------------|-----------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0.. |

Selector for the different stream channels.

See [GenTL specification 1.3 chapter 7](#) for more details.


6.2.3 StreamID

| Name | Stream ID |
|------------|-----------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Device unique ID for the stream, for instance a GUID.

See [GenTL specification 1.3 chapter 7](#) for more details.

7 Vimba1394TL DataStream Features



This chapter includes:

| | | |
|-------|------------------------------------|----|
| 7.1 | StreamInformation | 37 |
| 7.1.1 | StreamID | 37 |
| 7.1.2 | StreamType | 37 |
| 7.1.3 | StreamIsGrabbing [Allied Vision] | 38 |
| 7.2 | BufferHandlingControl | 38 |
| 7.2.1 | StreamAnnouncedBufferCount | 38 |
| 7.2.2 | StreamBufferHandlingMode | 39 |
| 7.2.3 | StreamAnnounceBufferMinimum | 39 |
| 7.2.4 | DriverBuffersCount [Allied Vision] | 39 |

This chapter lists features that are potentially available in this module. Some features are only available under certain circumstances.

The following categories can be found below the Root category:

- StreamInformation
- BufferHandlingControl

7.1 StreamInformation

Category that contains all Stream Information features of the Data Stream module.

See [GenTL specification 1.3 chapter 7](#) for more details.

7.1.1 StreamID

| Name | Stream ID |
|------------|-----------|
| Interface | IString |
| Access | Read |
| Visibility | Expert |

Device unique ID for the data stream, for instance a GUID.

Corresponds to the STREAM_INFO_ID command of DSGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

7.1.2 StreamType

| Name | Stream Type |
|------------|--------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | IIDC |

Transport layer type of the Data Stream.

See [GenTL specification 1.3 chapter 7](#) for more details.

7.1.3 StreamIsGrabbing [Allied Vision]

| Name | Stream Is Grabbing |
|------------|--------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Beginner |

Flag indicating whether the acquisition engine is started or not.

7.2 BufferHandlingControl

Contains all features of the Data Stream module that control the used buffers.

See [GenTL specification 1.3 chapter 7](#) for more details.

7.2.1 StreamAnnouncedBufferCount

| Name | Stream Announced Buffer Count |
|------------|-------------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Number of announced (known) buffers on this stream.

Corresponds to the STREAM_INFO_NUM_ANNOUNCED command of DSGetInfo function.

See [GenTL specification 1.3 chapter 7](#) for more details.

7.2.2 StreamBufferHandlingMode

| Name | Stream Buffer Handling Mode |
|------------|-----------------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Beginner |
| Values | Default |

Available acquisition modes of this stream.

See [GenTL specification 1.3 chapter 7](#) for more details.

7.2.3 StreamAnnounceBufferMinimum

| Name | Stream Announce Buffer Minimum |
|------------|--------------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Minimal number of buffers to announce to enable selected buffer handling mode.

Corresponds to the STREAM_INFO_BUF_ANNOUNCE_MIN command of DSGetInfo function.


See [GenTL specification 1.3 chapter 7](#) for more details.

7.2.4 DriverBuffersCount [Allied Vision]

| Name | Driver Buffers Count |
|------------|----------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Guru |
| Values | 3..1024 |

Number of driver buffers used by the acquisition engine.

8 Vimba1394TL Camera Features



This chapter includes:

| | | |
|------|--|-----|
| 8.1 | 1394 registers, FireGrab parameters and the Vimba1394TL features | 42 |
| 8.2 | DeviceControl | 44 |
| 8.3 | ImageFormatControl | 49 |
| 8.4 | AcquisitionControl | 62 |
| 8.5 | ExposureAutoControl [Allied Vision] | 71 |
| 8.6 | DigitalIOControl | 73 |
| 8.7 | SerialPortControl [Allied Vision] | 79 |
| 8.8 | AnalogControl | 85 |
| 8.9 | LUTControl | 90 |
| 8.10 | TransportLayerControl | 93 |
| 8.11 | UserSetControl | 98 |
| 8.12 | FileAccessControl | 101 |
| 8.13 | ColorTransformationControl | 106 |
| 8.14 | AutofunctionControl [Allied Vision] | 110 |
| 8.15 | ImageQualityControl [Allied Vision] | 113 |

This chapter lists features that are potentially available for Allied Vision cameras. Not all cameras have all the listed features, and some features are only available under certain circumstances.

The following categories can be found below the Root category:

- DeviceControl : see chapter DeviceControl
- ImageFormatControl : see chapter ImageFormatControl
- AcquisitionControl : see chapter AcquisitionControl
 - ExposureAutoControl : see chapter ExposureAutoControl [Allied Vision]
- DigitalIOControl : see chapter DigitalIOControl
 - SerialPortControl : see chapter SerialPortControl [Allied Vision]
- AnalogControl : see chapter AnalogControl
- LUTControl : see chapter LUTControl
- TransportLayerControl : see chapter TransportLayerControl
- UserSetControl : see chapter UserSetControl
- FileAccessControl : see chapter FileAccessControl
- ColorTransformationControl : see chapter ColorTransformationControl
- AutofunctionControl : see chapter AutofunctionControl [Allied Vision]
- ImageQualityControl : see chapter ImageQualityControl [Allied Vision]

8.1 1394 registers, FireGrab parameters and the Vimba1394TL features

The Vimba1394TL is GenICam-compliant. Therefore, some feature names differ from the IIDC standard and the FireGrab namings.

In order to ease the change, the table below lists:

- The IIDC names (known from the camera manuals)
- The FireGrab name
- The Vimba1394TL feature name
- An explanation, if applicable



The Vimba1394TL always works in Format_7 respectively FGP_SCALABLE, and FGP_DMAMODE is always set to DMA_CONTINUOUS

| IIDC Name | FireGrab | GenICam feature | Conversion |
|---------------------|----------------------|--------------------|---|
| IMAGE_SIZE.Width | FGP_XSIZE | Width | - |
| IMAGE_SIZE.Height | FGP_YSIZE | Height | - |
| IMAGE_POSITION.Left | FGP_XPOSITION | OffsetX | - |
| IMAGE_POSITION.Top | FGP_YPOSITION | OffsetY | - |
| SHUTTER | FGP_SHUTTER | ExposureTime | $ExposureTime = SHUTTER * TIMEBASE + EXPOSUREOFFSET$ |
| EXTD_SHUTTER | - | ExposureTime | $ExposureTime = EXTD_SHUTTER + EXPOSUREOFFSET$ |
| AUTO_EXPOSURE | FGP_AUTOEXPOSURE | ExposureAutoTarget | - |
| BRIGHTNESS | FGP_BRIGHTNESS | Blacklevel | - |
| GAIN | FGP_GAIN | Gain | $Gain = GAIN * GAINBASE$ |
| GAMMA | FGP_GAMMA | Gamma | GAMMA=0 => 1.0, else camera-dependent |
| WHITE_BALANCE.B | FGP_WHITEBALCB | BalanceRatioRaw | $BalanceRatioSelector = Green_Blue; BalanceRatioRaw = WHITE_BALANCE.B_Value$ |
| WHITE_BALANCE.R | FGP_WHITEBALCR | BalanceRatioRaw | $BalanceRatioSelector = Green_Red; BalanceRatioRaw = WHITE_BALANCE.B_Value$ |
| ISO_Speed_x | FGP_PHYSPEED | IIDCPhyspeed | (Enumeration) |
| - | FGP_FRAMEBUFFERCOUNT | DriverBuffersCount | - |
| BYTE_PER_PACKET | FGP_PACKETSIZE | IIDCPacketSize | see description of category Acquisition-Control |
| COLOR_CODING_ID | (FGP_IMAGEFORMAT) | PixelFormat | (Enumeration) |
| ISO_EN=1 | StartDevice() | AcquisitionStart | (Command) |
| ISO_EN=0 | StopDevice() | AcquisitionStop | (Command) |
| TRIGGER_MODE | FGP_TRIGGER | multiple | see description of category Acquisition-Control |
| SHUTTER | FGP_SHUTTER | ExposureAuto | values: |
| .A_M_Mode | .PVAL_AUTO | | Continuous/Off |
| .One_Push | .PVAL_ONESHOT | | Once |
| GAIN | FGP_GAIN | GainAuto | values: |
| .A_M_Mode | .PVAL_AUTO | | Continuous/Off |
| .One_Push | .PVAL_ONESHOT | | Once |
| WHITE_BALANCE | FGP_WHITEBALCB | BalanceWhiteAuto | values: |
| .A_M_Mode | .PVAL_AUTO | | Continuous/Off |
| .One_Push | .PVAL_ONESHOT | | Once |

Table 1: Translation of feature values known from IIDC/FireGrab

8.2 DeviceControl

In addition to the SFNC, this category provides the following features: *DeviceMicrocontrollerVersion*, *FirmwareVerMajor*, *FirmwareVerMajor* and *FirmwareVerBuild* let you inspect the firmware version of your camera in more detail and *DeviceSerialNumber* states details about the serial number.

DeviceStatusLightEnable allows to switch off the LED on the back side of your camera if needed in the physical camera setup.

To inspect or modify the register space of your 1394 camera, use *DeviceAccessRegisterAddress* and *DeviceAccessRegisterValue*.



Do not modify registers that are mapped in this XML file. The whole feature map may become inconsistent with your camera.

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.2.1 DeviceVendorName

| Name | Device Vendor Name |
|-------------------|--------------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Name of the manufacturer of the device.

See [SFNC](#) for more details.

8.2.2 DeviceModelName

| Name | Device Model Name |
|-------------------|-------------------|
| Interface | IString |
| Access | Read |
| Visibility | Beginner |

Model of the device.

See [SFNC](#) for more details.

8.2.3 DeviceFirmwareVersion

| Name | Device Firmware Version |
|------------|-------------------------|
| Interface | QString |
| Access | Read |
| Visibility | Beginner |

Version of the firmware in the device.

See [SFNC](#) for more details.

8.2.4 FirmwareVerMajor [Allied Vision]

| Name | Firmware Version Major |
|------------|------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Major firmware version of this Allied Vision 1394 camera.

8.2.5 FirmwareVerMinor [Allied Vision]

| Name | Firmware Version Minor |
|------------|------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Minor firmware version of this Allied Vision 1394 camera.

8.2.6 FirmwareVerBuild [Allied Vision]

| Name | Firmware Version Build |
|------------|------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Build firmware version of this Allied Vision 1394 camera.

8.2.7 DeviceMicrocontrollerVersion [Allied Vision]

| Name | Device Microcontroller Firmware Version |
|------------|---|
| Interface | String |
| Access | Read |
| Visibility | Beginner |

Version of the microcontroller firmware in the device.

8.2.8 DeviceSFNCVersionMajor

| Name | Device SFNCVersion Major |
|------------|--------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Major Version of the Standard Feature Naming Convention that was used to create the device's XML.
See [SFNC](#) for more details.

8.2.9 DeviceSFNCVersionMinor

| Name | Device SFNCVersion Minor |
|------------|--------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Minor Version of the Standard Feature Naming Convention that was used to create the device's XML.
See [SFNC](#) for more details.

8.2.10 DeviceSFNCVersionSubMinor

| Name | Device SFNCVersion Sub Minor |
|------------|------------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Sub Minor Version of Standard Feature Naming Convention that was used to create the device's XML.
See [SFNC](#) for more details.

8.2.11 DeviceID

| Name | Device ID |
|------------|-----------|
| Interface | String |
| Access | Read |
| Visibility | Expert |

Device Identifier (serial number).
See [SFNC](#) for more details.

8.2.12 DeviceSerialNumber [Allied Vision]

| Name | Device Serial Number |
|------------|----------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |

Serial number of the device as written on the camera label.

8.2.13 DeviceScanType

| Name | Device Scan Type |
|------------|------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | Areascan |

Scan type of the sensor of the device.

See [SFNC](#) for more details.

8.2.14 DeviceStatusLightEnable [Allied Vision]

| Name | Device Status Light Enable |
|------------|----------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Controls the LED status lights at the back side of the camera.

8.2.15 DeviceAccessRegisterAddress [Allied Vision]

| Name | Device Access Register Address |
|-------------------|--------------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Guru |
| Values | 4026532864..8589934588 |

The register address to access on the device.
Writing might render the feature node map invalid.

8.2.16 DeviceAccessRegisterValue [Allied Vision]

| Name | Device Access Register Value |
|-------------------|------------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Guru |

Value of a register on the device.

8.3 ImageFormatControl

By default, the Vimba1394TL sets the 1394 camera to IIDC Format 7 on startup. If this automatic behavior was disabled and the camera is in an IIDC Fixed Format, the command *IIDCActivateFormat7* may be invoked to return to normal operation.

Camera-specific modes are adjusted with the *IIDCMode* feature (see the camera manual, chapter Video formats, modes and bandwidth). For certain cameras, there is an accompanying feature *IIDCModeDescription*.

Since changes of the *IIDCMode* feature often influence binning or decimation of the image, the features *BinningHorizontal*, *BinningVertical*, *DecimationHorizontal*, or *DecimationVertical* also change. Nevertheless, they are only readable.

If the *PixelColorFilter* is incorrect, set *PixelColorFilterAuto* to *Manual* and adjust *PixelColorFilter* manually. If *ReverseX* or *ReverseY* are invoked, the available *PixelFormat* values (and the current *PixelFormat*) automatically change.

SensorBits gives you the bit depth of the used ADC (see camera manual for details).

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.3.1 SensorWidth

| Name | Sensor Width |
|-------------------|--------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Effective width of the sensor in pixels.

See [SFNC](#) for more details.

8.3.2 SensorHeight

| Name | Sensor Height |
|-------------------|---------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Effective height of the sensor in pixels.

See [SFNC](#) for more details.

8.3.3 SensorTaps

| Name | Sensor Taps |
|------------|--------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | One, Two |

Number of usable taps of the camera sensor.
See [SFNC](#) for more details.

8.3.4 SensorDigitizationTaps

| Name | Sensor Digitization Taps |
|------------|--------------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | One, Two |

Number of digitized samples outputted simultaneously by the camera A/D conversion stage.
See [SFNC](#) for more details.

8.3.5 SensorBits [Allied Vision]

| Name | Sensor Bits |
|------------|-------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Maximum bit depth of sensor.

8.3.6 Width

| Name | Width |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Width of the Image provided by the device (in pixels).
See [SFNC](#) for more details.

8.3.7 Height

| Name | Height |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Height of the image provided by the device (in pixels).
See [SFNC](#) for more details.

8.3.8 WidthMax

| Name | Maximum Width |
|------------|---------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Maximum Width of the Image provided by the device (in pixels).

See [SFNC](#) for more details.

8.3.9 HeightMax

| Name | Maximum Height |
|------------|----------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Maximum Height of the image provided by the device (in pixels).

See [SFNC](#) for more details.

8.3.10 OffsetX

| Name | Offset X |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0.. |

Horizontal offset from the origin to the area of interest (in pixels).

See [SFNC](#) for more details.

8.3.11 OffsetY

| Name | Offset Y |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0.. |

Vertical offset from the origin to the area of interest (in pixels).

See [SFNC](#) for more details.

8.3.12 BinningHorizontal

| Name | Binning Horizontal |
|------------|--------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |
| Values | 1..8 |

Number of horizontal photo-sensitive cells to combine together.

This increases the intensity (or signal-to-noise ratio) of the pixels and reduces the horizontal resolution (width) of the image. Only values 1, 2, 4 and 8 are supported.

See [SFNC](#) for more details.

8.3.13 BinningVertical

| Name | Binning Vertical |
|-------------------|------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |
| Values | 1..8 |

Number of vertical photo-sensitive cells to combine together.

This increases the intensity (or signal to noise ratio) of the pixels and reduces the vertical resolution (height) of the image. Only values 1, 2, 4 and 8 are supported.

See [SFNC](#) for more details.

8.3.14 DecimationHorizontal

| Name | Decimation Horizontal |
|-------------------|-----------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |
| Values | 1..8 |

Horizontal sub-sampling of the image.

This reduces the horizontal resolution (width) of the image by the specified horizontal decimation factor. Only values 1, 2, 4 and 8 are supported.

See [SFNC](#) for more details.

8.3.15 DecimationVertical

| Name | Decimation Vertical |
|------------|---------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |
| Values | 1..8 |

Vertical sub-sampling of the image.

This reduces the vertical resolution (height) of the image by the specified vertical decimation factor. Only values 1, 2, 4 and 8 are supported.

See [SFNC](#) for more details.

8.3.16 ReverseX

| Name | Reverse X |
|------------|------------|
| Interface | Boolean |
| Access | Read/Write |
| Visibility | Expert |

Flip horizontally the image sent by the device.

The ROI is applied after the flipping.

See [SFNC](#) for more details.

8.3.17 ReverseY

| Name | Reverse Y |
|------------|------------|
| Interface | Boolean |
| Access | Read/Write |
| Visibility | Expert |

Flip vertically the image sent by the device.

The ROI is applied after the flipping.

See [SFNC](#) for more details.

8.3.18 PixelFormat

| Name | Pixel Format |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Mono8, YUV411Packed, YUV422Packed, YUV444Packed, RGB8Packed, Mono16, RGB16Packed, BayerGR8, BayerRG8, BayerGB8, BayerBG8, BayerGR16, BayerRG16, BayerGB16, BayerBG16, Mono12Packed, BayerGR12Packed, BayerRG12Packed, BayerGB12Packed, BayerBG12Packed |

Format of the pixel provided by the device.

See [SFNC](#) for more details.

8.3.19 PixelColorFilter

| Name | Pixel Color Filter |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | None, BayerRG, BayerGB, BayerGR, BayerBG |

Type of color filter that is applied to the image.

See [SFNC](#) for more details.

8.3.20 PixelColorFilterAuto [Allied Vision]

| Name | Pixel Color Filter Auto |
|------------|-------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Manual, Auto |

Controls if the PixelColorFilter is determined automatically by the TL or if it can be manipulated.
Possible values:

- Manual: This enumeration value indicates that the PixelColorFilter may be manipulated.
- Auto: This enumeration value indicates that the PixelColorFilter is set automatically by the TL.

8.3.21 ImageSize [Allied Vision]

| Name | Image Size |
|------------|------------|
| Interface | IInteger |
| Access | Read |
| Visibility | Invisible |

Size of images, in bytes, for the current format and size.
Equivalent to PayloadSize for Allied Vision 1394 cameras.

8.3.22 TestImageSelector

| Name | Test Image Selector |
|------------|---|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Off, Img1("Image 1") [Allied Vision], Img2("Image 2") [Allied Vision], Img3("Image 3") [Allied Vision], Img4("Image 4") [Allied Vision] |

Selects the type of test image that is sent by the camera.

Selecting is only possible by index; no camera-specific mapping to certain test patterns is modeled.

Possible values:

- Off: No test image. Pure camera output.
- Img1: Test image 1. (Device-specific) [Allied Vision]
- Img2: Test image 2. (Device-specific) [Allied Vision]
- Img3: Test image 3. (Device-specific) [Allied Vision]
- Img4: Test image 4. (Device-specific) [Allied Vision]

See [SFNC](#) for more details.

8.3.23 IIDCActivateFormat7 [Allied Vision]

| Name | IIDC Activate Format 7 |
|------------|------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Use free modes (IIDC Format 7) of this camera.

Call this command for full functionality of this camera.

8.3.24 IIDCMode [Allied Vision]

| Name | IIDC Mode |
|-------------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Mode0, Mode1, Mode2, Mode3, Mode4, Mode5, Mode6, Mode7 |

The IIDC Format 7 Mode of this camera.

Select to implicitly change image format capabilities or sensor exposure modes. (See the camera manual.)

Possible values:

- Mode0: Select IIDC Mode 0 of this camera. (See the camera manual.)
- Mode1: Select IIDC Mode 1 of this camera. (See the camera manual.)
- Mode2: Select IIDC Mode 2 of this camera. (See the camera manual.)
- Mode3: Select IIDC Mode 3 of this camera. (See the camera manual.)
- Mode4: Select IIDC Mode 4 of this camera. (See the camera manual.)
- Mode5: Select IIDC Mode 5 of this camera. (See the camera manual.)
- Mode6: Select IIDC Mode 6 of this camera. (See the camera manual.)
- Mode7: Select IIDC Mode 7 of this camera. (See the camera manual.)

8.3.25 IIDCModeDescription [Allied Vision]

| Name | IIDC Mode Description |
|-------------------|---|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | BFullResolution("Full Resolution"), Binning_2H1V, Binning_4H1V, Binning_8H1V, Binning_1H2V, Binning_2H2V, Binning_4H2V, Binning_8H2V, Binning_1H4V, Binning_2H4V, Binning_4H4V, Binning_8H4V, Binning_1H8V, Binning_2H8V, Binning_4H8V, Binning_8H8V, DFullResolution("Full Resolution"), Decimation_2H1V, Decimation_4H1V, Decimation_8H1V, Decimation_1H2V, Decimation_2H2V, Decimation_4H2V, Decimation_8H2V, Decimation_1H4V, Decimation_2H4V, Decimation_4H4V, Decimation_8H4V, Decimation_1H8V, Decimation_2H8V, Decimation_4H8V, Decimation_8H8V |

The description of the format 7 mode of this IIDC camera.

Possible values:

- BFullResolution: The full resolution of the sensor is used.
- Binning_2H1V: Binning: 2x horizontal
- Binning_4H1V: Binning: 4x horizontal
- Binning_8H1V: Binning: 8x horizontal
- Binning_1H2V: Binning: 2x vertical
- Binning_2H2V: Binning: 2x horizontal, 2x vertical
- Binning_4H2V: Binning: 4x horizontal, 2x vertical
- Binning_8H2V: Binning: 8x horizontal, 2x vertical
- Binning_1H4V: Binning: 4x vertical
- Binning_2H4V: Binning: 2x horizontal, 4x vertical
- Binning_4H4V: Binning: 4x horizontal, 4x vertical
- Binning_8H4V: Binning: 8x horizontal, 4x vertical
- Binning_1H8V: Binning: 8x vertical
- Binning_2H8V: Binning: 2x horizontal, 8x vertical
- Binning_4H8V: Binning: 4x horizontal, 8x vertical
- Binning_8H8V: Binning: 8x horizontal, 8x vertical
- DFullResolution: The full resolution of the sensor is used.
- Decimation_2H1V: Sub-sampling: 2x horizontal
- Decimation_4H1V: Sub-sampling: 4x horizontal
- Decimation_8H1V: Sub-sampling: 8x horizontal
- Decimation_1H2V: Sub-sampling: 2x vertical
- Decimation_2H2V: Sub-sampling: 2x horizontal, 2x vertical
- Decimation_4H2V: Sub-sampling: 4x horizontal, 2x vertical
- Decimation_8H2V: Sub-sampling: 8x horizontal, 2x vertical
- Decimation_1H4V: Sub-sampling: 4x vertical
- Decimation_2H4V: Sub-sampling: 2x horizontal, 4x vertical
- Decimation_4H4V: Sub-sampling: 4x horizontal, 4x vertical
- Decimation_8H4V: Sub-sampling: 8x horizontal, 4x vertical
- Decimation_1H8V: Sub-sampling: 8x vertical
- Decimation_2H8V: Sub-sampling: 2x horizontal, 8x vertical
- Decimation_4H8V: Sub-sampling: 4x horizontal, 8x vertical
- Decimation_8H8V: Sub-sampling: 8x horizontal, 8x vertical

8.4 AcquisitionControl

One precondition for the Vimba1394TL is that *Deferred Transport* must not be invoked. In the case that it should be invoked (and hence acquisition doesn't seem to work correctly), it may be disabled with the *DeferredTransportDisable* command.

In the default case, the *AcquisitionFrameRate* may be controlled directly. This feature is closely connected to the *IIDCPacketSize* feature, and both of them may only be controlled if acquisition is not started. If *High-SNRImages* are set to a value greater than one, *AcquisitionFrameRate* will become unavailable because the frame rate then depends on the number of images that are added up plus a camera-specific delay and hence cannot be predicted.

The available values for the *TriggerSelector* depend on the *ExposureMode*. If *ExposureMode* is set to *TriggerWidth* (IIDC Trigger Mode 1), only *ExposureActive* can be selected in the *TriggerSelector*, while in *Timed* mode, *ExposureTime* may be controlled and *ExposureStart* and *AcquisitionStart* triggers are available. Due to the Allied Vision-specific routing of input lines as *TriggerSource*, the trigger source can only be determined in the *LineRouting* feature (if the *TriggerSource* is set to *InputLines*). Otherwise, *TriggerSource* may also have a value of *Software*, in which case the command *TriggerSoftware* becomes available. For hardware triggers (from Input lines), *TriggerActivation* and *TriggerDelay* may also be controlled.

In *Timed ExposureMode*, *ExposureTime* may be controlled directly. This time is the absolute time the sensor is exposed to light and already contains the minimum time the sensor is exposed (*ExposureOffset*) - as far as the camera reports this value.

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.4.1 AcquisitionMode

| Name | Acquisition Mode |
|-------------------|-------------------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | SingleFrame, MultiFrame, Continuous |

Sets the acquisition mode of the device.

It defines mainly the number of frames to capture during an acquisition and the way the acquisition stops.

See [SFNC](#) for more details.

8.4.2 AcquisitionStart

| Name | Acquisition Start |
|------------|-------------------|
| Interface | ICommand |
| Access | Write |
| Visibility | Beginner |

Starts the Acquisition of the device.

The number of frames captured is specified by AcquisitionMode.

See [SFNC](#) for more details.

8.4.3 AcquisitionStop

| Name | Acquisition Stop |
|------------|------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Stops the Acquisition of the device at the end of the current Frame.

It is mainly used when AcquisitionMode is Continuous but can be used in any acquisition mode.

See [SFNC](#) for more details.

8.4.4 AcquisitionAbort

| Name | Acquisition Abort |
|------------|-------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Invisible |

Stops the Acquisition of the device at the end of the current Frame.

It is mainly used when AcquisitionMode is Continuous but can be used in any acquisition mode. Only implemented as a synonym to AcquisitionStop to be compatible with GigE cameras.

See [SFNC](#) for more details.

8.4.5 AcquisitionFrameCount

| Name | Acquisition Frame Count |
|-------------------|-------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 1..65535 |

Number of frames to acquire in MultiFrame Acquisition mode.

See [SFNC](#) for more details.

8.4.6 AcquisitionFrameRate

| Name | Acquisition Frame Rate |
|-------------------|------------------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | FPS |
| Visibility | Beginner |

Controls the maximum acquisition rate (in Hertz) at which the frames are captured.

Not usable if HighSNRImages>0, external triggering or IIDCPacketSizeAuto are active.

See [SFNC](#) for more details.

8.4.7 AcquisitionFrameRateLimit [Allied Vision]

| Name | Acquisition Frame Rate Limit |
|------------|------------------------------|
| Interface | IFloat |
| Access | Read |
| textbfUnit | FPS |
| Visibility | Beginner |

This is the maximum frame rate possible for the current exposure duration and image format.

8.4.8 DeferredTransportDisable [Allied Vision]

| Name | Deferred Transport Disable |
|------------|----------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Disable Deferred Transport (see camera manual).

8.4.9 HighSNRImages [Allied Vision]

| Name | HighSNR Images |
|------------|----------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0..256 |

Number of images used for the HighSNR mode.

May influence the effective bit depth of the image. 0 disables HighSNR mode. Only values 2, 4, 8, 16, 32,

64, 128 and 256 are accepted, other values are changed to a valid value that's lower than the one that was set. If !=0, AcquisitionFrameRate is locked.

8.4.10 TriggerSelector

| Name | Trigger Selector |
|------------|---|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | ExposureStart, ExposureActive, AcquisitionStart |

Selects the type of trigger to configure.

See [SFNC](#) for more details.

8.4.11 TriggerMode

| Name | Trigger Mode |
|------------|--------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Off, On |

Controls if the selected trigger is active.

See [SFNC](#) for more details.

8.4.12 TriggerSoftware

| Name | Trigger Software |
|-------------------|------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Generates an internal trigger.
TriggerSource must be set to Software.
See [SFNC](#) for more details.

8.4.13 TriggerSource

| Name | Trigger Source |
|-------------------|--------------------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | InputLines [Allied Vision], Software |

Specifies the internal signal or physical input Line to use as the trigger source.
The selected trigger must have its TriggerMode set to On.
Possible values:

- InputLines: Specifies that physical lines (or pins) and associated I/O control blocks should be used as external source for the trigger signal. See the DigitalIOControl features. [Allied Vision]
- Software: Specifies that the trigger source will be generated by software using the TriggerSoftware command.

See [SFNC](#) for more details.

8.4.14 TriggerActivation

| Name | Trigger Activation |
|-------------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | FallingEdge, RisingEdge, LevelLow, LevelHigh |

Specifies the activation mode of the trigger.

See [SFNC](#) for more details.

8.4.15 TriggerDelay

| Name | Trigger Delay |
|-------------------|----------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | us |
| Visibility | Expert |
| Values | 0.0..2097151.0 |

Specifies the delay in microseconds (us) to apply after the trigger reception before activating it.

See [SFNC](#) for more details.

8.4.16 ExposureMode

| Name | Exposure Mode |
|-------------------|---------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Timed, TriggerWidth |

Sets the operation mode of the Exposure.

See [SFNC](#) for more details.

8.4.17 ExposureTime

| Name | Exposure Time |
|-------------------|---------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | us |
| Visibility | Beginner |

Sets the Exposure time (in microseconds) when ExposureMode is Timed.

This controls the duration where the photosensitive cells are exposed to light.

See [SFNC](#) for more details.

8.4.18 ExposureOffset [Allied Vision]

| Name | Exposure Offset |
|-------------------|-----------------|
| Interface | IFloat |
| Access | Read |
| textbfUnit | us |
| Visibility | Guru |

Exposure offset of this camera (in microseconds).
This is the minimum time that the sensor must be exposed to light.

8.4.19 ExposureTimeRaw

| Name | Exposure Time Raw |
|-------------------|-------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Sets the Exposure time (IIOC Shutter) when ExposureMode is Timed.
This controls the duration where the photosensitive cells are exposed to light.
See [SFNC](#) for more details.

8.4.20 ExposureAuto

| Name | Exposure Auto |
|-------------------|-----------------------|
| Interface | Enumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Off, Once, Continuous |

Sets the automatic exposure mode when ExposureMode is Timed.
For control of this feature see categories ExposureAutoControl and AutofunctionControl.
See [SFNC](#) for more details.

8.5 ExposureAutoControl [Allied Vision]

If *ExposureAuto* is enabled, only the standard IIDC shutter register is used internally, which means that the range for *ExposureTime* is limited (aka *ExposureAutoMin* and *ExposureAutoMax*). To influence this range, adjust the *ExposureAutoTimebase*. The default value is 20 μ s, resulting in a range of 20 to 81920 μ s plus *ExposureOffset* by default.

The algorithm by which the *ExposureAuto* feature works can be read out with feature *ExposureAutoAlg* (as in Allied Vision GigE cameras). For the *Mean* algorithm, the target value is *AutofunctionTargetIntensity*, which can be found in category AutofunctionControl [Allied Vision]. (For programs, feature *ExposureAutoTarget* is available as a synonym for *AutofunctionTargetIntensity*, as for GigE cameras).

8.5.1 ExposureAutoTimebase [Allied Vision]

| Name | Exposure Auto Timebase |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | tb1us, tb2us, tb5us, tb10us, tb20us, tb50us, tb100us, tb200us, tb500us, tb1000us |

Timebase used for the ExposureAuto feature.

Influences the minimum and the maximum of the ExposureTime, which can be seen in the min. of ExposureAutoMin and in the max. of ExposureAutoMax.

Possible values:

- tb1us: Use 1 microsecond as base for ExposureAuto.
- tb2us: Use 2 microseconds as base for ExposureAuto.
- tb5us: Use 5 microseconds as base for ExposureAuto.
- tb10us: Use 10 microseconds as base for ExposureAuto.
- tb20us: Use 20 microseconds as base for ExposureAuto.
- tb50us: Use 50 microseconds as base for ExposureAuto.
- tb100us: Use 100 microseconds as base for ExposureAuto.

- tb200us: Use 200 microseconds as base for ExposureAuto.
- tb500us: Use 500 microseconds as base for ExposureAuto.
- tb1000us: Use 1000 microseconds as base for ExposureAuto.

8.5.2 ExposureAutoMin [Allied Vision]

| Name | Exposure Auto Min |
|------------|-------------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | us |
| Visibility | Beginner |

Minimum exposure time in case that ExposureAuto is active, in microseconds.
To extend or limit the range, change ExposureAutoTimebase.

8.5.3 ExposureAutoMax [Allied Vision]

| Name | Exposure Auto Max |
|------------|-------------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | us |
| Visibility | Beginner |

Maximum exposure time in case that ExposureAuto is active, in microseconds.
To extend or limit the range, change ExposureAutoTimebase.

8.5.4 ExposureAutoTarget [Allied Vision]

| Name | Exposure Auto Target |
|-------------------|----------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Invisible |

The target image intensity for ExposureAuto in values from 0 to 255. Higher values result in brighter images. Equivalent to AutofunctionTargetIntensity.

8.5.5 ExposureAutoAlg [Allied Vision]

| Name | Exposure Auto Algorithm |
|-------------------|-------------------------|
| Interface | Enumeration |
| Access | Read |
| Visibility | Beginner |
| Values | Mean |

Algorithm used for ExposureAuto.
Possible values:

- Mean: Target a particular mean value of all measured pixels in the image (see ExposureAutoTarget).

8.6 DigitalIOControl

Allied Vision 1394 cameras are equipped with a number of input and output lines (called pins). Usually, there are more output lines than input lines. Line configuration can be done by first selecting a line with the *LineSelector* and then performing the necessary configuration that is appropriate for the type of line (*LineMode*, which can be *Input* or *Output*).

For each line, the *LineFormat* as well as the *LineStatus* may be determined, and the default polarity may be inverted with the *LineInverter* feature.

Each **input line** can be routed for use as a hardware trigger or not at all (with the feature *LineRouting*). Additionally, the *LineDebounceTime* may be adjusted if the camera supports this feature.

Each **output line** can be assigned a multitude of internal source signals (see *LineSource* enumeration): e.g. the *FrameActive* signal, the *Busy* signal or the corresponding input line. If applicable for your camera, a pulse width modulated signal may be selected as *LineSource*, which may be controlled with the features *LineModulationPulseWidth* and *LineModulationPeriod*.

Closely connected to the output signals, the internal *IntEna* signal may be controlled with the features *IntEnaDelayEnable* and *IntEnaDelayTime*.

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.6.1 LineSelector

| Name | Line Selector |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Line0("Input 1"), Line1("Input 2"), Line2("Input 3"), Line3("Input 4"), Line4("Output 1"), Line5("Output 2"), Line6("Output 3"), Line7("Output 4") |

Selects the physical line (or pin) of the external device connector to configure.

Line 0 to Line 3 correspond to input lines/pins and Line 4 to Line 7 correspond to output lines/pins.

See [SFNC](#) for more details.

8.6.2 LineMode

| Name | Line Mode |
|------------|---------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | Input, Output |

Shows if the physical Line is used to input or output a signal.

See [SFNC](#) for more details.

8.6.3 LineInverter

| | |
|-------------------|----------------------|
| Name | Line Inverter |
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Controls the inversion of the signal of the selected input or output Line.
See [SFNC](#) for more details.

8.6.4 LineStatus

| | |
|-------------------|--------------------|
| Name | Line Status |
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

The status of the selected input or output Line.
See [SFNC](#) for more details.

8.6.5 LineSource

| | |
|-------------------|--|
| Name | Line Source |
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Off, Direct [Allied Vision], ExposureActive, FrameValid [Allied Vision], Busy [Allied Vision], FollowInput [Allied Vision], PWM("PulseWidthModulation") [Allied Vision], FrameTrigger-Wait |

Selects which internal acquisition or I/O source signal to output on the selected Line.

LineMode must be Output. Refer to the camera manual to learn which Line Sources ("Output modes") are supported.

Possible values:

- Off: Line output is disabled.
- Direct: Line output follows LineStatus value. [Allied Vision]
- ExposureActive: Device is exposing a frame. Corresponds to the output mode IntegrationEnable explained in the camera manuals.
- FrameValid: Device is currently performing a readout from the sensor. [Allied Vision]
- Busy: Device is currently busy. [Allied Vision]
- FollowInput: Line output follows the state of the corresponding input line. [Allied Vision]
- PWM: Device is currently in Pulse Width Modulation mode. [Allied Vision]
- FrameTriggerWait: Device is currently waiting for a Frame trigger. Check the camera manual if your camera supports this Line Source (Output mode).

See [SFNC](#) for more details.

8.6.6 LineRouting [Allied Vision]

| Name | Line Routing |
|------------|--------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Off, Trigger |

Selects the routing of the selected input line ("Input mode").

LineMode must be Input.

Possible values:

- Off: Line input is disabled.
- Trigger: Line input is used for triggering. If you set more than one input to function as a trigger input, all trigger inputs are ANDed.

8.6.7 LineFormat

| Name | Line Format |
|-------------------|---------------------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Expert |
| Values | TTL, OptoCoupled("Optocoupled") |

Controls the current electrical format of the selected physical input or output Line.
See [SFNC](#) for more details.

8.6.8 LineDebounceTime [Allied Vision]

| Name | Line Debounce Time |
|-------------------|--------------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | us |
| Visibility | Expert |

Debounce time for the current input line (in microseconds).
May be set in steps of 0.5.

8.6.9 LineModulationPulseWidth [Allied Vision]

| Name | Line Modulation Pulse Width |
|-------------------|-----------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |
| Values | 1..16383 |

PWM pulse width.
LineMode must be Output.

8.6.10 LineModulationPeriod [Allied Vision]

| Name | Line Modulation Period |
|------------|------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |
| Values | ..16383 |

PWM period.
LineMode must be Output.

8.6.11 IntEnaDelayTime [Allied Vision]

| Name | IntEna Delay Time |
|------------|-------------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | us |
| Visibility | Expert |
| Values | 0..1048576 |

Delay time of the internal IntEna signal before being signaled at an output line, in microseconds.

8.6.12 IntEnaDelayEnable [Allied Vision]

| Name | IntEna Delay Enable |
|------------|---------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Enables the delay of the internal IntEna signal.

8.7 SerialPortControl [Allied Vision]

This category lists the IIDC serial port control features. Since the standard FileAccessControl mechanism does not fit, these features were added. For a description of the IIDC serial port controls, see the IIDC specification, version 1.31.

8.7.1 SerialPortSelector [Allied Vision]

| Name | Serial Port Selector |
|------------|----------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | IIDC |

Selects which serial port to use.

Possible values:

- IIDC: The IIDC 1.3.1 serial port feature is used.

8.7.2 SerialPortModeSelector [Allied Vision]

| Name | Serial Port Mode Selector |
|------------|------------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Off, Transmit, Receive, Both |

Selects which serial mode to use.

8.7.3 SerialPortBaudRate [Allied Vision]

| Name | Serial Port Baud Rate |
|------------|---|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Baud300, Baud600, Baud1200, Baud2400, Baud4800, Baud9600, Baud19200, Baud38400, Baud57600, Baud115200, Baud230400 |

This feature controls the baud rate used by the serial port.

8.7.4 SerialPortCharLength [Allied Vision]

| Name | Serial Port Char Length |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Length7Bits("7 bits"), Length8Bits("8 Bits") |

Selects which character length to use for serial I/O.

Possible values:

- Length7Bits: A length of 7 bits is used for serial I/O.
- Length8Bits: A length of 8 bits is used for serial I/O.

8.7.5 SerialPortParity [Allied Vision]

| Name | Serial Port Parity |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | None, Odd("Odd Parity"), Even("Even Parity") |

Selects which parity to use for serial I/O.

8.7.6 SerialPortStopBits [Allied Vision]

| Name | Serial Port Stop Bits |
|------------|---|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | StopBits1("1 Stop Bit"), StopBits1_5("1.5 Stop Bits"), StopBits2("2 Stop Bits") |

Selects how many stop bits to use for serial I/O.

8.7.7 SerialPortTransmitReady [Allied Vision]

| Name | Serial Port Transmit Ready |
|------------|----------------------------|
| Interface | IBoolean |
| Access | Read |
| Visibility | Expert |

Flag for indicating the status of the serial transmit operation.

8.7.8 SerialPortReceiveReady [Allied Vision]

| Name | Serial Port Receive Ready |
|------------|---------------------------|
| Interface | IBoolean |
| Access | Read |
| Visibility | Expert |

Flag for indicating the status of the serial receive operation.

8.7.9 SerialPortReceiveOverrunError [Allied Vision]

| Name | Serial Port Receive Overrun Error |
|------------|-----------------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Flag for indicating an overrun error as the result of the serial receive operation.
Set to Off to clear the error flag.

8.7.10 SerialPortReceiveFramingError [Allied Vision]

| Name | Serial Port Receive Framing Error |
|------------|-----------------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Flag for indicating a framing error as the result of the serial receive operation.
Set to Off to clear the error flag.

8.7.11 SerialPortReceiveParityError [Allied Vision]

| Name | Serial Port Receive Parity Error |
|------------|----------------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Flag for indicating a parity error as the result of the serial receive operation.
Set to Off to clear the error flag.

8.7.12 SerialPortBuffer [Allied Vision]

| Name | Serial Port Buffer |
|------------|--------------------|
| Interface | IRegister |
| Access | Read/Write |
| Visibility | Guru |

Serial port transfer buffer.
The same buffer is used for receive and transmit.

8.7.13 SerialPortValidReceiveSize [Allied Vision]

| Name | Serial Port Valid Receive Size |
|-------------------|--------------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |

Size of valid serial port receive data.

8.7.14 SerialPortRemainingReceiveSize [Allied Vision]

| Name | Serial Port Remaining Receive Size |
|-------------------|------------------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |

Size of remaining serial port receive data.

8.7.15 SerialPortTransmitSize [Allied Vision]

| Name | Serial Port Transmit Size |
|-------------------|---------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |

Size of the serial port transmit buffer.

8.8 AnalogControl

Allied Vision features in this category: *GainAutoTarget* as a synonym for *AutofunctionTargetIntensity*, *GammaRaw* as a feature to control the IIDC Gamma feature directly (usually not available), and *BalanceRatioRaw* to control the IIDC "WhiteBalance" register directly.

The *...Raw* features in this category correspond directly to the register values of the corresponding IIDC registers and may not be accessible if there is a better control available via a non-*...Raw* feature. IIDC users should know that *BlackLevel* corresponds to the IIDC "Brightness" register and that the Auto mode of IIDC "WhiteBalance" is controllable via the *BalanceWhiteAuto* feature.



Note that *Gamma* and *LUT* features influence each other.

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.8.1 GainSelector

| Name | Gain Selector |
|-------------------|---------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | All |

Selects which Gain is controlled by the various Gain features.

See [SFNC](#) for more details.

8.8.2 Gain

| Name | Gain |
|-------------------|------------|
| Interface | IFloat |
| Access | Read/Write |
| textbfUnit | dB |
| Visibility | Beginner |

Controls the selected gain as an absolute physical value (in dB).

This is an amplification factor applied to the video signal.

See [SFNC](#) for more details.

8.8.3 GainRaw

| Name | Gain Raw |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Raw value of the gain feature.

See [SFNC](#) for more details.

8.8.4 GainAuto

| Name | Gain Auto |
|------------|-----------------------|
| Interface | Enumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Off, Once, Continuous |

Sets the automatic gain control (AGC) mode.

For control of this feature see category `AutofunctionControl`.

See [SFNC](#) for more details.

8.8.5 GainAutoTarget [Allied Vision]

| Name | Gain Auto Target |
|------------|------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Invisible |

The target image intensity for GainAuto in values from 0 to 255.
Higher values result in brighter images. Equivalent to AutofunctionTargetIntensity.

8.8.6 BlackLevelSelector

| Name | Black Level Selector |
|------------|----------------------|
| Interface | Enumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | All |

Selects which Black Level is controlled by the various Black Level features.
See [SFNC](#) for more details.

8.8.7 BlackLevel

| Name | Black Level |
|------------|-------------|
| Interface | IFloat |
| Access | Read/Write |
| Visibility | Expert |

Controls the analog black level as an absolute physical value.

This represents a DC offset applied to the video signal.

See [SFNC](#) for more details.

8.8.8 Gamma

| Name | Gamma |
|------------|------------|
| Interface | IFloat |
| Access | Read/Write |
| Visibility | Beginner |
| Values | ..1.0 |

Controls the gamma correction of pixel intensity.

This is typically used to compensate for non-linearity of the display system (such as CRT).

See [SFNC](#) for more details.

8.8.9 GammaRaw [Allied Vision]

| Name | Gamma Raw |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |

Controls the steps of the gamma correction of pixel intensity.

This is typically used to compensate for non-linearity of the display system (such as CRT).

8.8.10 BalanceRatioSelector

| Name | Balance Ratio Selector |
|------------|---|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Green_Red("Green / Red") [Allied Vision], Green_Blue("Green / Blue") [Allied Vision], IID-CVR [Allied Vision], IIDCUB [Allied Vision] |

Selects which Balance ratio to control.

Possible values:

- Green_Red: Balance Ratio will be applied to the green (low values) or red (high values) channel. [Allied Vision]
- Green_Blue: Balance Ratio will be applied to the green (low values) or blue (high values) channel. [Allied Vision]
- IIDCVR: Balance Ratio will be applied to the V or R channel. [Allied Vision]
- IIDCUB: Balance Ratio will be applied to the U or B channel. [Allied Vision]

See [SFNC](#) for more details.

8.8.11 BalanceRatioRaw [Allied Vision]

| Name | Balance Ratio Raw |
|------------|-------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |

Raw value of the BalanceRatio.

8.8.12 BalanceWhiteAuto

| | |
|-------------------|---------------------------|
| Name | Balance White Auto |
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Off, Once, Continuous |

Controls the mode for automatic white balancing between the color channels. The white balancing ratios are automatically adjusted. For control of this feature see category AutofunctionControl.

See [SFNC](#) for more details.

8.9 LUTControl

LUT control via SFNC features works by two mechanisms: Selecting a (pre-defined) LUT is done via *LUTSelector*, while enabling it can be done via the *LUTEnable* feature. Since in Allied Vision 1394 cameras, only one LUT is usable, this means that to enable a different LUT, you have to disable the active LUT first (by having the *LUTSelector* set to the active LUT and setting *LUTEnable* to *Off*). Additionally, using the *Gamma* feature influences LUT usage in Allied Vision 1394 cameras, so keep in mind that usage of one of them influences the state of the other one.

Supplementary information for uploading LUT data is available with the following features:

- *LUTCount*, the number of available LUTs
- *LUTSizeBytes*, the number of bytes a complete LUT needs
- *LUTBitDepthIn*, the number of used data bits before the LUT transformation
- *LUTBitDepthOut*, the number of used data bits after the LUT transformation

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.9.1 LUTSelector

| Name | LUT Selector |
|------------|---|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Luminance("Luminance 1"), Luminance2 [Allied Vision], Luminance3 [Allied Vision], Luminance4 [Allied Vision], Luminance5 [Allied Vision], Luminance6 [Allied Vision], Luminance7 [Allied Vision], Luminance8 [Allied Vision], Luminance9 [Allied Vision], Luminance10 [Allied Vision], Luminance11 [Allied Vision], Luminance12 [Allied Vision], Luminance13 [Allied Vision], Luminance14 [Allied Vision], Luminance15 [Allied Vision], Luminance16 [Allied Vision] |

Selects which LUT to control.

See [SFNC](#) for more details.

8.9.2 LUTEnable

| Name | LUT Enable |
|------------|------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Activates the selected LUT.

See [SFNC](#) for more details.

8.9.3 LUTCount [Allied Vision]

| Name | LUT Count |
|-------------------|-----------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

The number of user look-up tables.

8.9.4 LUTSizeBytes [Allied Vision]

| Name | LUT Size |
|-------------------|----------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

The size for a complete LUT in bytes.

8.9.5 LUTBitDepthIn [Allied Vision]

| Name | LUT Bit Depth In |
|-------------------|------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |
| Values | ..16 |

The used bit depth of pixel data before applying the LUT conversion.
This value determines the number of LUT entries.

8.9.6 LUTBitDepthOut [Allied Vision]

| Name | LUT Bit Depth Out |
|-------------------|-------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

The bit depth of pixel data after the LUT conversion was applied.
This value corresponds to the bit depth of each LUT value.

8.10 TransportLayerControl

Beside the standard feature *PayloadSize*, there are many IIDC-related features in this category and some FireGrab-specific.

- *IIDCPhyspeed* controls the speed of the asynchronous and the isochronous transfer on the bus the camera is connected to.
- By comparing the *IIDCBusNumber* for two cameras, you may determine if the cameras are connected to the same IIDC bus, which may be important if you have to share the bandwidth between them.
- *IIDCFreeBandwidth* gives you the available bandwidth on the bus the camera is connected to.
- Normally, the ISO channel is determined automatically. You can change this by switching *IIDC-IsoChannelAuto* to *Off* and then setting the *IsoChannel* feature to the desired value.
- After some write operations on camera registers, the system waits and lets the camera device process data for *IIDCCameraAcceptDelay* milliseconds. By default, this time is set to 3 milliseconds.
- The *IIDCPacketCount* is a result of the selected packet size per cycle.
- The *IIDCPacketSize* may determined directly if the *IIDCPacketSizeAuto* feature is set to *Off*. In this case, both features, *IIDCPacketSize* and *AcquisitionFrameRate* both influence the used packet size. If *IIDCPacketSizeAuto* feature is set to *Maximize*, always the largest possible packet size is chosen to achieve a maximum frame rate.
- At this time, *IIDCPacketSizeMaximum* is a read-only feature which is only available if the corresponding camera feature *MaxIsoPacketSize* was activated at the start of the transport layer. In this case, you may switch to the standard packet size with the command *IIDCUseStandardPacketSizeMaximum*.

8.10.1 PayloadSize

| Name | Payload Size |
|-------------------|--------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Provides the number of bytes transferred for each image or chunk on the stream channel. This includes any end-of-line, end-of-frame statistics or other stamp data. This is the total size of data payload for a data block.

See [SFNC](#) for more details.

8.10.2 IIDCPhyspeed [Allied Vision]

| Name | IIDC Physical Speed |
|-------------------|------------------------|
| Interface | Enumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | S100, S200, S400, S800 |

Specifies the physical speed on the bus for this camera.

Possible values:

- S100: Specifies that the speed used on the bus will be 100 Mb/s.
- S200: Specifies that the speed used on the bus will be 200 Mb/s.
- S400: Specifies that the speed used on the bus will be 400 Mb/s.
- S800: Specifies that the speed used on the bus will be 800 Mb/s.

8.10.3 IIDCFreeBandwidth [Allied Vision]

| Name | IIDC Free Bandwidth |
|------------|---------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |
| Values | 0.. |

Bandwidth per 1394 bus cycle that is currently available for allocation on the bus <IIDCBusNumber>.

8.10.4 IIDCPacketSizeMaximum [Allied Vision]

| Name | IIDC Packet Size Maximum |
|------------|--------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Expert |

Maximum of the Packet Size per 1394 bus cycle.

Only available if the MaxIsoSize feature of this camera is enabled.

8.10.5 IIDCUseStandardPacketSizeMaximum [Allied Vision]

| Name | IIDC Use Standard Packet Size Maximum |
|------------|---------------------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Deactivate the MaxIsoSize feature of this camera (see camera manual).

Resets the maximum packet size limit to the IIDC limits. Only available if the MaxIsoSize feature of this camera is enabled. If you experience problems with AcquisitionStart, please run this command.

8.10.6 IIDCPacketSizeAuto [Allied Vision]

| Name | IIDC Packet Size Auto |
|-------------------|-----------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Off, Maximize |

Automatically set the IIDCPacketSize.

If this feature is activated, neither IIDCPacketSize nor AcquisitionFrameRate may be set.

Possible values:

- Off: Packet Size may be controlled directly.
- Maximize: If activated, IIDCPacketSize is set to the maximum possible after changes to IIDCPhyspeed, Width, Height and PixelFormat.

8.10.7 IIDCPacketSize [Allied Vision]

| Name | IIDC Packet Size |
|-------------------|------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Expert |

Packet Size per 1394 bus cycle.

8.10.8 IIDCPacketCount [Allied Vision]

| Name | IIDC Packet Count |
|-------------------|-------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Guru |

The number of packets used for the current transfer.

8.10.9 IIDCCameraAcceptDelay [Allied Vision]

| Name | IIDC Camera Accept Delay |
|-------------------|--------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Guru |
| Values | ..20000 |

After some writes on camera registers the system waits and lets the camera device process data, in milliseconds.

This time by default is set to 3 milliseconds.

8.10.10 IIDCIsoChannelAuto [Allied Vision]

| Name | IIDC Iso Channel Auto |
|-------------------|-----------------------|
| Interface | Enumeration |
| Access | Read/Write |
| Visibility | Guru |
| Values | Off, On |

Controls the mode for selecting the isochronous channel for the transfer.

Possible values:

- Off: Manual selection of isochronous channel.
- On: Internal resource manager handles channel assignment.

8.10.11 IIDCIsoChannel [Allied Vision]

| Name | IIDC Iso Channel |
|------------|------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Guru |
| Values | 0.. |

Selects the isochronous channel for the transfer.

8.10.12 IIDCBusNumber [Allied Vision]

| Name | IIDC Bus Number |
|------------|-----------------|
| Interface | Integer |
| Access | Read |
| Visibility | Guru |

The number of the firewire bus that this device is attached to.

8.11 UserSetControl

As an extension to the standard features in this category, *UserSetOperationStatus* and *UserSetOperationResult* may be queried after the *UserSetLoad* and *UserSetSave* commands. Since the default user set may only be determined under certain circumstances, only a command *UserSetMakeDefault* is available. For more general information, see the [GenICam Standard Features Naming Convention](#).

8.11.1 UserSetSelector

| Name | User Set Selector |
|------------|---------------------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Beginner |
| Values | Default, UserSet1, UserSet2, UserSet3 |

Selects the feature User Set to load, save or configure.
See [SFNC](#) for more details.

8.11.2 UserSetLoad

| Name | User Set Load |
|------------|---------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Loads the User Set specified by UserSetSelector to the device and makes it active.
See [SFNC](#) for more details.

8.11.3 UserSetSave

| Name | User Set Save |
|------------|---------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Save the User Set specified by UserSetSelector to the non-volatile memory of the device.
See [SFNC](#) for more details.

8.11.4 UserSetMakeDefault [Allied Vision]

| Name | User Set Make Default |
|-------------------|-----------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Makes the current User Set the default User Set used when the device is reset.

8.11.5 UserSetOperationStatus [Allied Vision]

| Name | User Set Operation Status |
|-------------------|---------------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Guru |
| Values | Success, Failure |

Represents the User Set operation execution status.

Possible values:

- Success: The recent user set operation was successful.
- Failure: The recent User Set operation failed.

8.11.6 UserSetOperationResult [Allied Vision]

| Name | User Set Operation Result |
|-------------------|---------------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Guru |

Represents the user set operation result.

8.12 FileAccessControl

Category that contains the File Access control features.

See [SFNC](#) for more details.

8.12.1 FileSelector

| Name | File Selector |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Guru |
| Values | ShadingData [Allied Vision], LUTLuminance("LUT Luminance 1"), LUTLuminance2 [Allied Vision], LUTLuminance3 [Allied Vision], LUTLuminance4 [Allied Vision], LUTLuminance5 [Allied Vision], LUTLuminance6 [Allied Vision], LUTLuminance7 [Allied Vision], LUTLuminance8 [Allied Vision], LUTLuminance9 [Allied Vision], LUTLuminance10 [Allied Vision], LUTLuminance11 [Allied Vision], LUTLuminance12 [Allied Vision], LUTLuminance13 [Allied Vision], LUTLuminance14 [Allied Vision], LUTLuminance15 [Allied Vision], LUTLuminance16 [Allied Vision] |

Selects the target file in the device.

Possible values:

- ShadingData: Shading data for the camera. [Allied Vision]
- LUTLuminance: The Luminance 1 LUT of the camera.
- LUTLuminance2: The Luminance 2 LUT of the camera. [Allied Vision]
- LUTLuminance3: The Luminance 3 LUT of the camera. [Allied Vision]
- LUTLuminance4: The Luminance 4 LUT of the camera. [Allied Vision]
- LUTLuminance5: The Luminance 5 LUT of the camera. [Allied Vision]
- LUTLuminance6: The Luminance 6 LUT of the camera. [Allied Vision]
- LUTLuminance7: The Luminance 7 LUT of the camera. [Allied Vision]
- LUTLuminance8: The Luminance 8 LUT of the camera. [Allied Vision]
- LUTLuminance9: The Luminance 9 LUT of the camera. [Allied Vision]
- LUTLuminance10: The Luminance 10 LUT of the camera. [Allied Vision]
- LUTLuminance11: The Luminance 11 LUT of the camera. [Allied Vision]
- LUTLuminance12: The Luminance 12 LUT of the camera. [Allied Vision]
- LUTLuminance13: The Luminance 13 LUT of the camera. [Allied Vision]
- LUTLuminance14: The Luminance 14 LUT of the camera. [Allied Vision]

- LUTLuminance15: The Luminance 15 LUT of the camera. [Allied Vision]
- LUTLuminance16: The Luminance 16 LUT of the camera. [Allied Vision]

See [SFNC](#) for more details.

8.12.2 FileStatus [Allied Vision]

| Name | File Status |
|-------------------|--------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Guru |
| Values | Closed, Open |

Represents the status of the selected file.

Possible values:

- Closed: File is closed.
- Open: File is open.

8.12.3 FileOperationSelector

| Name | File Operation Selector |
|-------------------|--------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Guru |
| Values | Open, Close, Read, Write |

Selects the target operation for the selected file in the device.

This Operation is executed when the FileOperationExecute feature is called.

See [SFNC](#) for more details.

8.12.4 FileOperationExecute

| Name | File Operation Execute |
|------------|------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Guru |

Executes the operation selected by FileOperationSelector on the selected file.

See [SFNC](#) for more details.

8.12.5 FileOpenMode

| Name | File Open Mode |
|------------|------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Guru |
| Values | Read, Write, ReadWrite |

Selects the access mode in which a file is opened in the device.

See [SFNC](#) for more details.

8.12.6 FileAccessBuffer

| Name | File Access Buffer |
|------------|--------------------|
| Interface | IRegister |
| Access | Read/Write |
| Visibility | Guru |

Defines the intermediate access buffer that allows the exchange of data between the device file storage and the application.

See [SFNC](#) for more details.

8.12.7 FileAccessOffset

| Name | File Access Offset |
|-------------------|--------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Guru |

Controls the Offset of the mapping between the device file storage and the FileAccessBuffer.

See [SFNC](#) for more details.

8.12.8 FileAccessLength

| Name | File Access Length |
|-------------------|--------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Guru |
| Values | 0.. |

Controls the Length of the mapping between the device file storage and the FileAccessBuffer.

See [SFNC](#) for more details.

8.12.9 FileOperationStatus

| Name | File Operation Status |
|-------------------|-----------------------|
| Interface | IEnumeration |
| Access | Read |
| Visibility | Guru |
| Values | Success, Failure |

Represents the file operation execution status.

See [SFNC](#) for more details.

8.12.10 FileOperationResult

| Name | File Operation Result |
|-------------------|-----------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Guru |

Represents the file operation result.

For Read or Write operations, the number of successfully read/written bytes is returned.

See [SFNC](#) for more details.

8.12.11 FileSize

| Name | File Size |
|-------------------|-----------|
| Interface | Integer |
| Access | Read |
| Visibility | Guru |

Represents the size of the selected file in bytes.

See [SFNC](#) for more details.

8.13 ColorTransformationControl

The standard color transformation control features are extended by a *ColorTransformationReset* command, which resets the values in the camera to the default values, which were normally determined with a light source of 5500K.

Additionally, controls for *Hue* and *Saturation* can also be found in this category.

For more general information, see the [GenICam Standard Features Naming Convention](#).

8.13.1 ColorTransformationSelector

| Name | Color Transformation Selector |
|------------|-------------------------------|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | RGBtoRGB |

Selects which Color Transformation module is controlled by the various Color Transformation features.

See [SFNC](#) for more details.

8.13.2 ColorTransformationEnable

| Name | Color Transformation Enable |
|------------|-----------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Activates the selected Color Transformation module.

See [SFNC](#) for more details.

8.13.3 ColorTransformationReset [Allied Vision]

| Name | Color Transformation Reset |
|------------|----------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Expert |

Resets the color transformation matrix to the factory values.
(Usually resulting in a 5500K setup.)

8.13.4 ColorTransformationValueSelector

| Name | Color Transformation Value Selector |
|------------|--|
| Interface | IEnumeration |
| Access | Read/Write |
| Visibility | Expert |
| Values | Gain00, Gain01, Gain02, Gain10, Gain11, Gain12, Gain20, Gain21, Gain22 |

Selects the Gain factor of the Transformation matrix to access in the selected Color Transformation module.

See [SFNC](#) for more details.

8.13.5 ColorTransformationValue

| Name | Color Transformation Value |
|------------|----------------------------|
| Interface | IFloat |
| Access | Read/Write |
| Visibility | Expert |
| Values | -1.000001..2.000001 |

Represents the value of the selected Gain factor inside the Transformation matrix.
See [SFNC](#) for more details.

8.13.6 Hue [Allied Vision]

| Name | Hue |
|------------|------------|
| Interface | IFloat |
| Access | Read/Write |
| Visibility | Beginner |

Float value of the Hue feature (in degrees).
Only has a visible effect in YUV and RGB modes.

8.13.7 HueRaw [Allied Vision]

| Name | Hue Raw |
|------------|------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Raw value of the Hue feature.
Only has a visible effect in YUV and RGB modes.

8.13.8 HueEnable [Allied Vision]

| Name | Hue Enable |
|------------|------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Enables control of the Hue feature.
Only has a visible effect in YUV and RGB modes.

8.13.9 Saturation [Allied Vision]

| Name | Saturation |
|------------|------------|
| Interface | IFloat |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0.0..2.0 |

Float value of the Saturation feature.
Only has a visible effect in YUV and RGB modes.

8.13.10 SaturationRaw [Allied Vision]

| Name | Saturation Raw |
|------------|----------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Raw value of the Saturation feature.
Only has a visible effect in YUV and RGB modes.

8.13.11 SaturationEnable [Allied Vision]

| Name | Saturation Enable |
|------------|-------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Expert |

Enables control of the Saturation feature.
Only has a visible effect in YUV and RGB modes.

8.14 AutofunctionControl [Allied Vision]

This category contains features for controlling algorithms for some "Auto" features (*ExposureAuto*, *GainAuto*, *BalanceWhiteAuto*).

The target intensity for *ExposureAuto* and *GainAuto* is determined by *AutoFunctionTargetIntensity*, and *BalanceWhiteAuto* always aims at equilibrating the three color components. All algorithms may be locally restricted to an area in the current image by setting *AutofunctionAOIWidth*, *AutofunctionAOIHeight* etc. and then setting *AutofunctionAOIEnable* to *True*. As a visual feedback, set *AutofunctionAOIShowArea* to *True*.

8.14.1 AutofunctionTargetIntensity [Allied Vision]

| Name | Autofunction Target Intensity |
|------------|-------------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

The target image intensity for *ExposureAuto* and *GainAuto* in values from 0 to 255.
Higher values result in brighter images.

8.14.2 AutofunctionAOIEnable [Allied Vision]

| Name | Autofunction AOI Enable |
|------------|-------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Beginner |

Use Autofunction AOI.

ExposureTime, Gain and BalanceRatio may be influenced by this feature (if the corresponding Auto features are enabled).

8.14.3 AutofunctionAOIShowArea [Allied Vision]

| Name | Autofunction AOI Show Area |
|------------|----------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Beginner |

Show the AOI used for Auto functions (ExposureAuto, GainAuto and BalanceWhiteAuto). This feature will only have a visible effect if AutofunctionAOIEnable is On.

8.14.4 AutofunctionAOIWidth [Allied Vision]

| Name | Autofunction AOI Width |
|------------|------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Width of the Autofunction AOI.

8.14.5 AutofunctionAOIHeight [Allied Vision]

| Name | Autofunction AOI Height |
|------------|-------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Height of the Autofunction AOI.

8.14.6 AutofunctionAOIOffsetX [Allied Vision]

| Name | Autofunction AOI Offset X |
|------------|---------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0.. |

Autofunction AOI left position.

8.14.7 AutofunctionAOIOffsetY [Allied Vision]

| Name | Autofunction AOI Offset Y |
|------------|---------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |
| Values | 0.. |

Autofunction AOI top position.

8.15 ImageQualityControl [Allied Vision]

To compensate for intensity irregularities of lenses or illumination, the "Shading..." features in this category may be used.

With feature *SmearReductionEnable*, you may reduce the amount of smearing in some camera types.

For a more detailed description of the features in this category, see the camera manual.

8.15.1 ShadingCorrectionEnable [Allied Vision]

| Name | Shading Correction Enable |
|------------|---------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Beginner |

Enable usage of shading correction data.

8.15.2 ShadingCorrectionShowData [Allied Vision]

| Name | Shading Correction Show Data |
|------------|------------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Beginner |

Show shading correction data instead of normal camera output.

8.15.3 ShadingDataBuildImages [Allied Vision]

| Name | Shading Data Build Images |
|------------|---------------------------|
| Interface | Integer |
| Access | Read/Write |
| Visibility | Beginner |

Number of images to use for a ShadingDataBuild command.

8.15.4 ShadingDataBuild [Allied Vision]

| Name | Shading Data Build |
|------------|--------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Build shading data.

The number of images used is determined by ShadingDataBuildImages.

8.15.5 ShadingDataLoadFromFlash [Allied Vision]

| Name | Shading Data Load From Flash |
|------------|------------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Loads the shading data from the flash memory.

8.15.6 ShadingDataSaveToFlash [Allied Vision]

| Name | Shading Data Save To Flash |
|------------|----------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Saves the shading data to the flash memory.

8.15.7 ShadingDataClearFlash [Allied Vision]

| Name | Shading Data Clear Flash |
|------------|--------------------------|
| Interface | ICommand |
| Access | Read/Write |
| Visibility | Beginner |

Clears the shading data in the flash memory.

8.15.8 ShadingDataMaxSize [Allied Vision]

| Name | Shading Data Max Size |
|------------|-----------------------|
| Interface | Integer |
| Access | Read |
| Visibility | Beginner |


Maximum size of shading data.

8.15.9 SmearReductionEnable [Allied Vision]

| Name | Smear Reduction Enable |
|------------|------------------------|
| Interface | IBoolean |
| Access | Read/Write |
| Visibility | Beginner |

Enable smear reduction.

9 Vimba functional extensions to GenTL



This chapter includes:

- 9.1 Custom Transport Layer events 118
 - 9.1.1 Additions to EVENT_TYPE_LIST 118
 - 9.1.2 Additions to EVENT_DATA_INFO_CMD_LIST . . . 118
 - 9.1.3 Additional enumeration IFCHANGE_WHAT_LIST . 118
- 9.2 Additional URL information 119
 - 9.2.1 Additions to URL_INFO_CMD_LIST 119

Vimba transport layers provide additional functionality to the general GenTL interface. The provided extensions to Transport Layer Events allow monitoring system changes. Other extensions allow comfortable access to additional URL information.

9.1 Custom Transport Layer events

Custom additions to the following Enumerations are available:

- EVENT_TYPE_LIST (used in GCRegisterEvent and GCUnregisterEvent)
- EVENT_DATA_INFO_CMD_LIST (used in EventGetDataInfo)

Additionally, an enumeration for determining the type of a change is provided: IFCHANGE_WHAT_LIST

These extensions allow the users of Vimba transport layers to get informed about changes to either the interface list or the camera list.

9.1.1 Additions to EVENT_TYPE_LIST

Listing 1: Event types

```
enum EVENT_TYPE_LIST_VIMBA
{
    EVENT_SYSTEM_CHANGE          = 1000, // System detected some change
    EVENT_INTERFACE_CHANGE       = 1001  // Interface detected some change
}
```

9.1.2 Additions to EVENT_DATA_INFO_CMD_LIST

Listing 2: Change Events

```
enum EVENT_DATA_INFO_CMD_LIST_VIMBA
{
    // for event type EVENT_SYSTEM_CHANGE
    EVENT_DATA_SYSTEM_IFCOUNT = 1000, // UINT32    Number of detected interfaces

    // for event type EVENT_INTERFACE_CHANGE
    EVENT_DATA_IFCHANGE_DUID    = 1001, // STRING    Device UID
    EVENT_DATA_IFCHANGE_WHAT    = 1002, // UINT32    Bitfield of what has changed
                                     // (IFCHANGE_WHAT_LIST)
    EVENT_DATA_IFCHANGE_DATA    = 1003  // UINT32    Bitfield of current state of
                                     // the device (IFCHANGE_WHAT_LIST)
};
```

9.1.3 Additional enumeration IFCHANGE_WHAT_LIST

Listing 3: Change Event options

```
enum IFCHANGE_WHAT_LIST
{
    IFCHANGE_WHAT_VISIBILITY    = 1,    // Device visibility has changed
    IFCHANGE_WHAT_REACHABILITY  = 2    // Device reachability has changed
};
```

9.2 Additional URL information

For the following Enumeration, extensions are available:

- URL_INFO_CMD_LIST (used in GCGetPortURLInfo)

The extensions allow the user of the Vimba transport layers to access URL information without having to parse the URL string.

9.2.1 Additions to URL_INFO_CMD_LIST

Listing 4: URL information

```
enum URL_INFO_CMD_LIST_VIMBA
{
    URL_INFO_FILENAME          = 1000,  // STRING    Filename of the port XML file
    URL_INFO_ADDRESS           = 1001,  // UINT64    Start address of the XML file
    URL_INFO_LENGTH            = 1002,  // SIZET     XML file length (in bytes)
    URL_INFO_ZIPPED            = 1003   // BOOL8     Is the XML file zipped
};
```