

DOCUMENTS OVERVIEW

Vimba Quickstart Guide

V2.0 2016-Feb-22

Vimba tools for every purpose

Vimba is the all-in-one solution for working with Allied Vision cameras.

- Vimba Viewer: The fastest way to get an image
- Development: APIs for C, C++, and .NET, with codingexamples
- Third-party applications: GenICam-compliant transport layers, Vimba Cognex Adapter

Vimba Viewer

Use *Vimba Viewer* to instantly view images from your Allied Vision camera and to try out camera features without any programming.

Using Vimba Viewer

- 1. Connect the camera to the PC.
- 2. Start *Vimba Viewer*. The *Camera Selector* opens.
- 3. In the Camera Selector, to open a camera, click the appropriate list item:



Figure 1: Camera Selector, opening a camera by default

The Main window opens automatically.

4. To start image acquisition, click the **Freerun button**:



Figure 2: Main window, starting image acquisition

V2.0 Page 1 of 6



GigE/CL cameras, grayed out Freerun button

GigE cameras

In this case, the *Main window* is in *Config Mode* to allow the configuration of the interface settings.

5. Correct the interface settings:




Figure 3: Main window, configuring the GigE interface settings

- 6. After correcting the interface settings, close the *Main window*.
- 7. In the Camera Selector, to open a camera, right-click the appropriate list item.
- 8. Click Open FULL ACCESS:




Figure 4: Camera Selector, opening a camera

The Main window opens automatically.

9. Start image acquisition, see Step 4.

Goldeye CL cameras

Use *Vimba Viewer* to configure Goldeye CL cameras and set features. To acquire images, use the software provided by the frame grabber manufacturer.

V2.0 Page 2 of 6



More information on camera installation



Further information available online

Select your Allied Vision camera on our website and find detailed information in its installation manual:

https://www.alliedvision.com/en/support/technical-documentation.html

Development

Depending on your programming language and the camera interface, different documents are relevant.

In any case, starting with the *Vimba Manual* is recommended. To ease programming with *Vimba*, read the documentation in the order suggested in the table below:



Documentation availability

The documentation is available for the installed components only.

Reading order	Component	Documentation	x = necessary / o = optional						
			С	C++	.NET	1394	GigE	USB	CL
1	Vimba	Vimba Manual.pdf	Х	Х	Х				
2	Vimba C API	Vimba C Manual.pdf	Х						
	Vimba C++ API	Vimba CPP Manual.pdf		Х					
	Vimba .NET API	Vimba NET Manual.pdf			Х				
3	Camera Features	Vimba1394TLFeaturesManual.pdf				X			
		GigE_Features_References.pdf					Х		
		USB_Features_Reference.pdf						Х	
		Goldeye_Features_Reference.pdf							Х
4	Vimba Features	Vimba Features Manual.pdf	Х	Х	Χ				
5	Vimba Image Transform Library	Vimba ImageTransform Manual.pdf	0	0					
6	Transport Layer	Vimba1394TLFeaturesManual.pdf				0			
		VimbaGigETLFeaturesManual.pdf					0		
		VimbaUSBTLFeaturesManual.pdf						0	
		VimbaCLConfigTLFeaturesManual.pdf							0

Table 1: Manuals for the developer

Windows only

V2.0 Page 3 of 6



Coding examples

For a practical introduction to *Vimba* coding, **Vimba Examples** are helpful.



Linux coding examples

Linux does not provide access via start menu or ExamplesOverview.hta. Under *Linux*, see in the *Vimba* installation directory:

- VimbaCPP/Examples
- VimbaC/Examples




Figure 5: Windows Start Menu, access to Vimba Examples

In the Examples directory, ExamplesOverview.hta provides an overview of and links to the enclosed examples:




Figure 6: ExamplesOverview.hta (Windowsonly)

V2.0 Page 4 of 6



Third-party applications

Vimba provides GenlCam-compliant TLs (transport layers) for GigE, USB, 1394, and Goldeye CL cameras from Allied Vision. To use these cameras with a third-party application, read the documentation in the order suggested in Table 2:




Applications non-compliant with GenICam

After the *Vimba* installation, GenlCam-compliant third-party applications automatically find and use the *Vimba* TL.

For third-party applications not compliant with GenlCam, read the corresponding manual.

Reading order	Component	ponent Documentation		x = necessary o = optional					
			IEEE 1394	GigE	USB	CL			
1	GenICam-compliant third-party applications	Please read the documentation of the third-party application. Depending on the third-party application, also see the following:							
2	Camera Features	Vimba1394TLFeaturesManual.pdf	Х						
		GigE_Features_References.pdf		Х					
		USB_Features_Reference.pdf			Х				
		Goldeye_Features_Reference.pdf				Χ			
3	Transport Layer	Vimba1394TLFeaturesManual.pdf	0						
		VimbaGigETLFeaturesManual.pdf		0					
		VimbaUSBTLFeatures Manual.pdf			0				
		VimbaCLConfigTLFeaturesManual.pdf				0			

Table 2: Manuals for the third-party application user





Cognex Adapter

Cognex VisionPro is supported by the Vimba CognexAdapter (Windows only). For more information see Vimba Cognex Manual.pdf.

For extended functionality of the *Vimba Cognex Adapter*, see Vimba1394TLFeaturesManual.pdf, GigEFeaturesReferences.pdf, USBFeaturesReference.pdf, or Goldeye_Features_Reference.pdf.

V2.0 Page 5 of 6



Contact us

Technical information:

https://www.alliedvision.com

Support:

https://www.alliedvision.com/en/support/contact-support-and-repair.html

Allied Vision Technologies GmbH Taschenweg 2a 07646 Stadtroda, Germany

Tel: +49 36428-677-0 Fax: +49 36428-677-28 Email: info@alliedvision.com

Disclaimer

For the latest version of this document, please visit our website. All trademarks are acknowledged as property of their respective owners. Copyright © 2016 Allied Vision Technologies GmbH.

V2.0 Page 6 of 6